

INSTALLATION INSTRUCTIONS FOR MDC V3.1 UPDATE

These instructions describe how to upgrade MDC v3.0 to MDC v3.1 using the MDC UPDATE.

If you are installing the software from CD or disks please skip to step 2.

1. If you are retrieving this software via the Internet, download the MDC31PATCH.EXE file from the website into an **EMPTY**, temporary subdirectory on your computer (**NOT** C:\TEMP). This is a self-extracting PKZIP file containing all of the databases, program files and executables needed for the program. After downloading the file, type MDC31PATCH at the DOS prompt of that subdirectory. The file should unzip itself into the subdirectory. You may also double click the icon for that file in Windows 95/NT Explorer.
2. Close any open applications, and run the file SETUP.EXE from the subdirectory, CD or the Run option on the Start Menu in Windows 95/NT.
3. Follow the prompts for identifying subdirectories that the program will update.
4. Initiate the program by double clicking on the new MDC icon from the appropriate Program Group off the Start Menu.
5. If you have questions, contact Perrin Quarles Associates, Inc. (tel 804-979-3700 or e-mail mdc@pqa.com).

Updating Tables

When running the MDC software for the first time after upgrading to a new version of the software, the following screen may appear during the tables merge process.

The screenshot shows a Windows-style dialog box titled "Formula Codes (RT 520)". It contains two sections for table comparison:

- Section 1:** "Your Selected Table:" with Value: "19-1" and Label: "19-1 (Emission rate using Cd,Fd,O2w)".
- Section 2:** "The Reference Table:" with Value: "19-1" and Label: "19-1 (Emission rate using Cd,Fd,O2d)".

Below these sections, a message states: "There is a potential conflict in the table entries above. Please select an option from the choices below." At the bottom, there are six buttons arranged in two columns:

- Left Column: "Ignore - Use Selected Table Value", "Make Selected Table Equal Reference Table", "Make Reference Table Equal Selected Table".
- Right Column: "Abort - Do NOT Merge Tables", "Edit Selected Table Value", "Edit Reference Table Value".

This screen indicates that the tables merge program has discovered a difference between your current tables file (Your Selected Table) and the new tables file (The Reference Table). To allow the tables merge program to update your tables file select **Make Selected Table Equal Reference Table** (Recommended). If you wish to keep your existing table entries and not update the your tables file select **Ignore - Use Selected Table Value**. To change the value in your current tables file select **Edit Selected Table Value**. The **Abort - Do NOT Merge Tables** button will cancel the merge process and exit the program.