

June 1991

SOIL TRANSPORT AND FATE DATABASE 2.0
AND
MODEL MANAGEMENT SYSTEM

by

Ronald C. Sims
Judith L. Sims
Steven G. Hansen

Department of Civil and Environmental Engineering
Utah State University
Logan, Utah 84322-4110

Project Officer:

John E. Matthews
Robert S. Kerr Environmental Research Laboratory
P.O. Box 1198
Ada, Oklahoma 74820

ROBERT S. KERR ENVIRONMENTAL RESEARCH LABORATORY
OFFICE OF RESEARCH AND DEVELOPMENT
U.S. ENVIRONMENTAL PROTECTION AGENCY
ADA, OKLAHOMA 74820

ACKNOWLEDGMENTS

Assistance in organizing and preparing the Soil Transport and Fate Database Version 2.0 was obtained from Stephanie Toombs, Karyn Dinerstein and James Herrick of the Department of Civil and Environmental Engineering, Utah State University.

TABLE OF CONTENTS

Introduction to the Soil Transport and Fate Database 2.0 and Model Management System	1
Description of Soil Transport and Fate Database 2.0 and Model Management System	1
 PART I	
Description of Soil Transport and Fate Database 2.0	2
STF 2.0 Files	3
Identification	3
Chemical Characteristics	3
Immobilization	5
Transformation/Degradation	8
Toxicity	8
Bioconcentration	10
References	10
Getting Started with STF 2.0	12
STF 2.0 Operation Modes	13
Directory Operating Mode	13
View Operating Mode	14
Filter Operating Mode	16
Report Operating Mode	18
 PART II	
Description of the VIP and RITZ Model Editors	20
Getting Started with VME and RME	20
RME and VME Operating Mode	21
Running VME and RME Input Files in VIP and RITZ Models	23
 REFERENCES	24
 APPENDICES	
Appendix A: Installation Instructions	25
Appendix B: Color Options	29
Appendix C: Tutorial	33
Appendix D: STF Database 2.0 Chemical List	39
Appendix E: STF 2.0 Files and Associated Information	47
Appendix F: List of Journals, Documents, and Reports Cited	59

INTRODUCTION TO THE SOIL TRANSPORT AND FATE DATABASE 2.0 AND MODEL MANAGEMENT SYSTEM

Version 1.0 of the Soil Transport and Fate Database (STF) was released in October 1988. This update of the Database (Version 2.0) incorporates recent research findings as well as modifications and changes suggested by users and the U.S. EPA Project Officer.

DESCRIPTION OF SOIL TRANSPORT AND FATE DATABASE 2.0 AND MODEL MANAGEMENT SYSTEM

The Soil Transport and Fate Database 2.0 and Model Management System (referred to as the "System") consists of three categories. The first category contains the Soil Transport and Fate Database 2.0 (STF 2.0). The second category contains the VIP model editor (VME) and the RITZ model editor (RME). These editors interface directly with STF 2.0. The third category contains the VIP and RITZ models and are included for convenience.

Minimal instructions on the use of the VIP and RITZ models as part of the System are presented in this manual. Please refer directly to the respective user's manuals (Nofziger et al., 1988; Stevens et al., 1988; Stevens et al., 1989) for in depth inquiries as to the theory or applications of the VIP and RITZ models.

The System is automatically entered the first time as part of the installation process. Thereafter, The System is entered by typing STF at the root directory prompt (typically C:\). Upon typing STF, the User is presented with the System menu, from which the desired application is chosen.

Instruction for use of the System is divided into two parts. Part I covers the STF 2.0 and Part II covers the VME and RME interface programs.

PART I

DESCRIPTION OF SOIL TRANSPORT AND FATE DATABASE 2.0

The Soil Transport and Fate (STF 2.0) Database 2.0 provides quantitative and qualitative information concerning the behavior of organic and a few inorganic chemicals (comprised of the Appendix VIII constituents listed in 40 CFR Part 261) in soil environments. The chemicals have been characterized for soil chemical processes using literature data. Soil chemical processes characterized include:

- * Degradation;
- * Transformation;
- * Partitioning among the water, soil, air, and oil phases comprising a soil system;
- * Toxicity; and
- * Propensity to bioaccumulate.

Additional information in the STF 2.0 Database includes chemical properties data and literature citations. The User therefore can access the source of data or information found in STF 2.0. A list of journals and documents cited in STF 2.0 is provided in Appendix F. In most cases, only data generated since 1980 have been included in data files containing information on chemical properties, toxicity, and bioaccumulation. The major emphasis was to include data generated since 1987 for the fate of chemicals in soil environments.

The STF Database is a tool for EPA personnel involved with contaminated site assessment and remediation activities. The STF Database may be used to provide input data concerning degradation rates, partition coefficients, and chemical property data for mathematical models simulating the behavior and fate of chemical constituents in contaminated surface and subsurface soils, either through the direct extraction of data from STF 2.0 into the VIP and RITZ model editors, or by creating reports for using data in other models or applications. The information is also useful for providing assistance in determining treatment potential at contaminated sites using in situ techniques. Chemicals may be evaluated with respect to the importance of natural processes in controlling persistence and transport potential and therefore the susceptibility to degradation or retardation within a soil or subsurface environment.

STF 2.0 FILES

STF 2.0 is divided into seven separate files. Two of these files, IDENTIFICATION and REFERENCES, are designed to help the User find and/or access data referenced in STF 2.0. Five additional files, CHEMICAL CHARACTERISTICS, IMMOBILIZATION, TRANSFORMATION/ DEGRADATION, TOXICITY and BIOCONCENTRATION, provide specific information for each of the chemicals found in STF 2.0. General information and definitions of the parameters in the STF 2.0 files are explained below:

* IDENTIFICATION

This file contains an alphabetical list (included in Appendix D) of the approximately 400 chemicals included in the STF 2.0 Database. From this list, the User selects the chemical for which information is required. The IDENTIFICATION file includes: (1) the STF chemical name, which, in most cases, is the name given in 40 CFR Part 261, Appendix VIII; and identification number (most of which are Chemical Abstract Service (CAS) numbers- if no CAS number was available, a unique STF number was assigned to the chemical in the form 999-00-*, where * ranges from 1-5; and (2) common names for each chemical).

* CHEMICAL CHARACTERISTICS (also referred to as “Chemicals”)

This file contains information concerning physical and chemical characteristics of the chemicals included in the STF 2.0 Database. For information presented that is not otherwise qualified, the User should assume a standard temperature of 25°C. Additional information about a parameter or important information that does not fit a specific parameter field are included in the memo. The User is strongly advised to always consult the memo. Parameters found in this file are defined below.

Use or Occurrence: The purpose for which the chemical was adopted or where it occurs in the environment.

Formula: The relative number of atoms of each type of element in the chemical; given as the number of carbons followed by the number of hydrogens followed by any other elements in alphabetical order.

Molecular Mass (g/mol): The mass obtained by adding the masses of all the atoms in the molecular formula of a substance.

Vapor Pressure (torr): The pressure exerted by the vapor (gas) of a substance when it is under equilibrium conditions with its own vapor.

Viscosity (g/cm-s): The resistance to change of form (liquid) or gradual yielding to forces tending to change their form (solids); the lower the viscosity, the greater the mobility of the substance.

Specific Gravity (dimensionless): The ratio of the mass of a body to the mass of an equal volume of water at 4 °C or other specified temperature.

Melting Point (°C): The temperature at which a solid substance undergoes a phase change to a liquid.

Boiling Point (°C): The temperature at which the vapor pressure of a liquid equals the atmospheric pressure.

Henry's Law Constant (dimensionless): The ratio of the partial pressure of a compound in air to the concentration of the compound in water at a given temperature under equilibrium conditions; the greater the value for Henry's Law constant, the greater the tendency of the compound to volatilize from aqueous solution.

Diffusivity Coefficient, Air (sq. cm/s): The measure of the rate of diffusion (process by which the substance mixes with air) of a substance in air.

Diffusivity Coefficient, Water (sq. cm/s): The measure of the rate of diffusion (process by which the substance mixes with water) of a substance in water.

Gibb's Free Energy (kcal/mol): The thermodynamic function of state, which is constant during a reversible isobaric - isothermic process (thermodynamic potential); a measure of the spontaneity of a reaction.

Log Octanol-Water (dimensionless): Partition coefficient; ratio of the concentration of the compound in octanol relative to the concentration of the compound in water; a measurement of the extent to which a substance partitions itself between octanol and water. The greater the Kow value of a compound, the smaller will be its tendency to move with the aqueous phase in the subsurface.

Acid Dissociation Constant (pKa):

$$pK_a = \frac{-\log [H^+][A^-]}{HA}$$

where HA is the acid and A- is the conjugate base; the greater the pKa, the weaker the substance as an acid.

Solubility in Water (mg/l): The saturated concentration of the concentration of the compound in water at a given temperature and pressure. Compounds with high water solubilities tend to desorb from soils and sediments and are less likely to volatilize from water (they will tend to migrate further with the aqueous flow component than those with low solubilities).

Detection Limit in Aqueous Medium: The lower limit for accurate measurement that is affected by interfering substances and by the analytical method and instrument.

EPA Guidance Concentration: The suggested EPA quality standard for the compound in air (ug/m³), water (ug/L), and soil (ug/g).

Analytical Method: The technique for extracting the compound from a given medium. For most chemicals, the analytical method is a recommended EPA test method.

*** IMMOBILIZATION (also referred to as “Immobility”)**

This file contains information concerning partitioning, immobility, and transport of the chemicals in a soil environment. Additional information about each chemical is located in either of the two memos for the chemical. The User is strongly advised to consult these memos. Parameters found in this file are defined below.

SOIL TYPE AND CONDITIONS

Soil Name: Soil name is given as the series from the USDA soil classification system. If the series classification name was not given, the soil name was assigned a site location/topography descriptor.

Texture: Relative proportions of the various soil separates (sand, silt, and clay) in a soil as described by the classes of soil texture presented in the United States Department of Agriculture (USDA) “texture triangle.”

pH Range: Range of the acidity (or alkalinity) of the soil, where pH is the negative logarithm of the hydrogen ion activity of the soil.

Average Temperature: The mean thermal temperature measurement of the soil or the temperature at which the soil was maintained.

Average Moisture Content: The mean amount of water retained by absorption when water is free to move through a mass of soil.

SOIL PROPERTIES

Permeability (cm/d): The readiness with which a porous medium (the soil) transmits water.

Cation Exchange Capacity (cmol/kg): The measure of the quantity of readily exchangeable cations (positive ions) neutralizing negative charges in the soil; the quantity of cations adsorbed on soil-particle surfaces per unit mass of the soil under chemically neutral conditions.

Organic Carbon (%): The difference between the total carbon (%) and the inorganic carbon (%) in the soil; most organic carbon is contained in the soil organic fraction (cells of microorganisms, plant and animal residues, highly carbonized compounds such as graphite and coal, etc.); inorganic carbon is mostly present in carbonate materials.

Saturated Water Content (fraction): The fraction, by weight or volume, at which the water content is equal to the porosity of the soil.

Saturated Hydraulic Conductivity: The ratio of the flux of water to the hydraulic gradient in saturated soil.

Porosity:

$$\text{Total porosity} = 1 - \frac{\text{bulk density}}{\text{particle density}}$$

Bulk Density (g/cm³): The ratio of the mass of dry soil to its total volume (solids and pores together). Weight soil/volume soil.

Particle Effective Size (mm): The tenth percentile size (ten percent of particles, by weight, are smaller than the 'particle effective size').

WASTE PROPERTIES

Constituent Concentration (g/m³): The concentration of a chemical in the medium of concern.

Mass Fraction of Oil: The fraction by weight of oil in a waste.

Mass Fraction of Water: The fraction by weight of water in a waste.

Density of Oil (g/cm³): The ratio of mass of oil to volume of oil.

Viscosity of Oil (cp): An indication of the ease with which a compound will flow; the lower the viscosity, the greater will be the mobility of the compound.

Log K_o: oil/water partition coefficient;

$$\text{Log } K_o = \log (C_o / C_w)$$

where C_o is the concentration of the chemical in the oil phase, and C_w is the concentration of the chemical in the aqueous phase.

Log K_h : Henry's Law constant;

$$\log K_h = \log (C_a / C_w)$$

where C_a is the concentration of the chemical in the air phase and C_w is the concentration of the chemical in the aqueous phase.

Log K_d : Soil/water partition coefficient;

$$\text{Log } K_d = \log (C_s / C_w)$$

where C_s is the concentration of the chemical in the soil (solid) phase and C_w is the concentration of the chemical in the aqueous phase.

K_f : Freundlich isotherm; an adsorption isotherm for the chemical is obtained using the Freundlich sorption equation. The linear form of this equation is:

$$\text{Log } X = \text{Log } K_f + 1/n \text{ Log } C$$

where X = mg of chemical per kg of soil, C = equilibrium solution concentration, and K_f and $1/n$ are the constants that characterize the adsorption capacity for the chemical. When $1/n = 1.0$, $K_f = K_d$ (soil/water partition coefficient).

$1/n$: Measurement of the intensity of adsorption reflecting the degree to which adsorption is a function of concentration.

r^2 : Coefficient of determination; a number between 0 and 1, showing how much of a relationship in correlation is due to the factors being compared; for example, 0.7 means 70 percent of variation in the dependent variable is caused by the independent variable (R^2 is not the same as R , the correlation coefficient, which ranges between -1 and +1).

Log K_{oc} : soil/sediment partition (sorption) coefficient; ratio of adsorbed chemical per unit weight of organic carbon in the soil to the concentration of the chemical in solution at equilibrium. A low K_{oc} (high water solubility) indicates a tendency to desorb from soils and sediments (less likely to volatilize from water).

Log K_{oa} : oil/water partition coefficient;

$$\log K_{oa} = \log (C_o / C_a)$$

where C_o is the concentration of the chemical in the oil phase, and C_a is the concentration of the chemical in the air phase.

Log K_{sa} : soil/air partition coefficient;

$$\log K_{sa} = \log (C_s / C_a)$$

where C_s is the concentration of the chemical in the soil phase, and C_a is the concentration of the chemical in the air phase.

Scale: Method by which the data were attained is identified numerically in the following manner:

1. calculated value
2. experimentally determined in a laboratory
3. value obtained from field studies

*** TRANSFORMATION/DEGRADATION (also referred to as “Transformation”)**

This file contains information concerning degradation and transformation processes of the chemicals in a soil environment. Additional information about each chemical is located in either of the two memos for the chemical. The User is strongly advised to consult these memos.

With exception of the parameters defined below, parameters in TRANSFORMATION/DEGRADATION are the same as those in IMMOBILIZATION. Please refer to IMMOBILIZATION for definitions of those parameters found in both files.

C_o (mg/kg): The initial concentration of the chemical in the medium.

K (1/day): Rate constant for a first order reaction. Fast reactions have a large K value.

$t(1/2)$ (days): The time necessary for half of the substance initially present to react (time required for the concentration of a reactant to decrease to half its initial value); for first order reactions, $t(1/2) = 0.693/k$.

r^2 : coefficient of determination; a number between 0 and 1, showing how much of a relationship in correlation is due to the factors being compared; for example, 0.7 means 70 percent of variation in the dependent variable is caused by the independent variable (R^2 is not the same as R , the correlation coefficient, which ranges between -1 and +1).

*** TOXICITY**

This file contains information concerning toxicity for the chemicals included in the Database. Additional information on a chemical is located in either of the two memos for the chemical. In TOXICITY, the first memo appears on the screen; however if it is too lengthy to view completely, the memo should be entered. Instructions on how to enter memos is presented in the next section. The User is strongly advised to consult these memos.

Carcinogenic Risk: Determination of whether exposure to an agent has the potential to increase the incidence of cancer (and how likely a chemical is to be a human carcinogen).

Reference Dose: For systemic toxicants, an estimate of a daily exposure to the human population (including sensitive subgroups) that is likely to be without an appreciable risk of deleterious effects during a lifetime.

Risk Specific Dose: For carcinogens, environmental concentrations that, under specified intake assumptions, correspond to excess lifetime cancer risks of 10^{-6} for class A and B carcinogens, or 10^{-5} for Class C carcinogens.

LC 50 (mg/L): The median lethal concentration; the concentration of the chemical that will produce death in 50 percent of the target population.

LD 50 (mg/L): The median lethal dose; the dosage of the chemical that will produce death in 50 percent of the treated animals.

EC 50: Chemical concentration affecting a specific response (e.g., respiration, loss of equilibrium) by 50% in a given time; in the Microtox(TM) test, sample concentrations resulting in a 50 percent decrease of light produced by the luminescent bacteria. Higher EC 50 values indicate lower toxicity than lower values.

Assay: A toxicity test utilizing organisms to determine toxicological effects. The two microbial bioassays commonly cited in this database are the Ames 'Salmonella typhimurium' mammalian microsome assay and the Microtox(TM) system.

Ames: Measure of the mutagenic potential of hazardous compounds; special strains of 'Salmonella typhimurium' that require histidine to grow are used to test for mutagenicity. When plated on a histidine-free medium, the only bacteria able to form colonies are those that have reverted to the "wild" state and are able to produce their own histidine. Without the addition of test chemicals, this back mutagen occurs at a rate specific to each strain type (spontaneous reversion rate). The addition of chemicals that are mutagenic increases the reversion rate.

Microtox(TM): Aqueous general toxicity assay that measures the reduction in light output produced by a suspension of marine luminescent bacteria ('Photobacterium phosphoreum') in response to an environmental sample. Bioluminescence of the test organism depends on a complex chain of biochemical reactions. Chemical inhibition of any of the biochemical reactions causes a reduction in bacterial luminescence.

Mutagenic Ratio: The ratio of the number of colonies that form in the presence of a test sample to the number of colonies in the absence of a test sample (control growth plate);
mutagenic ratio = # of colonies counted/spontaneous revertants.

Mutagenic Dose: Mutation/Metabolic Activation Dose

Scale: Method by which data were attained is identified numerically in the following manner:

1. Calculated value
2. Experimentally determined in a laboratory
3. Value obtained from field studies

*** BIOCONCENTRATION**

This file contains information concerning bioconcentration potential of the chemicals included in the Database. Additional information for each chemical is included in the memo for the chemical. In the BIOCONCENTRATION file, the memo appears on the screen; however if it is too lengthy to view completely, the memo should be entered. Instructions on how to enter memos is presented in the next section.

Log K_{ow} : The ratio of the concentration of the compound relative to the concentration of the compound in water; a measurement of the extent to which a substance partitions itself between octanol and water; the greater the K_{ow} , the smaller will be its tendency to move with the aqueous phase in the subsurface.

Log Bioconcentration (Log BCF): The concentration of the chemical in the organism at equilibrium divided by the concentration of the chemical in the organism's environment (air, water, soil, etc.).

*** REFERENCES**

Information presented in this file is provided so that the User may access the literature source from which information contained in STF 2.0 was compiled. Data in all files, except IDENTIFICATION, are accompanied by a "Short Reference". This "Short Reference" lists the author's and co-author's names and is the link to the full reference citation. The full reference is accessed through the identification number.

Not all references used in the Database are primary sources of information. The type of information source used is identified in this file in a numerical manner:

<u>Source No.</u>	<u>Type of Reference</u>
1	Refereed Journal
2	Non-refereed Journal
3	Government Report
4	Book; Standard Reference

When searching in the REFERENCE file, the exact location of a specific author's contribution is found by referring to the Reference type (2-6), corresponding with the numbers in the selection mode found in each file. For example, 2 indicates "Chemical," meaning that this reference corresponds to data found in the CHEMICAL CHARACTERISTICS file for the selected chemical. In that file, the author's name or "Short Reference" will be found next to the particular contribution. The reference types are given as follows:

- 2. Chemical
- 3. Immobility
- 4. Transformation
- 5. Toxicity
- 6. Bioconcentration

In STF 2.0 Database files that contain a reference to **Scale**, "1" refers to calculated data, "2" refers to a value determined experimentally in laboratory, pilot or bench scale studies, and "3" refers to data obtained from field studies.

GETTING STARTED WITH STF 2.0

Once the System Menu has been entered by typing STF at the root directory prompt (typically C:\), the User must then select menu option “S” to enter STF 2.0.

After a few seconds the title page or Introduction appears. Page two of the introduction presents the User with four options:

- 1) Entering the introductory HELP memo by typing H;
- 2) Entering INSTALL PRINTER by typing P;
- 3) Entering COLORS by typing C; and,
- 4) Entering the STF 2.0 operation modes by striking any other key.

The introductory HELP memo provides an overview of STF 2.0 and contains the introductory instructions that are presented in this section. Once the operation modes have been entered, the User cannot return to the Introduction without exiting and reentering STF 2.0. However, it is unlikely that the User will need to view the HELP memo in the introduction once the operation modes have been entered since additional HELP memos are provided at specific locations in the program.

The INSTALL PRINTER option allows the User to set printer conditions for reports that are generated within STF 2.0. The default command provided is “CHR(15)”. This is the command for compressed print for dot matrix type printers. Laser printers have unique compressed print commands and therefore documentation provided with the specific printer should be consulted. Compressed print is recommended due to the large size of reports that may be generated. However, the User may designate any command string acceptable to the printer.

The COLORS option allows the User to change the default colors used for data presentation in STF 2.0, VME and RME. A list of color selections is provided in Appendix B. The syntax must be followed precisely to ensure that the command strings are accepted by the STF 2.0 program.

The STF 2.0 operation modes are entered by striking any other key. Before a key is struck, the printer should be setup as desired since it is not possible to return to the introduction without first exiting STF 2.0. Upon striking a key, the User enters one of the operation modes, i.e., the “Directory” mode, and is presented with an alphabetical listing of the chemicals found in the Database. This chemical list is presented as part of the IDENTIFICATION file.

STF 2.0 OPERATION MODES

The STF 2.0 can be operated in four different modes. These four modes are Directory, View, Filter and Report. The User will determine in which mode to operate based on intended use. The User, however, is able to switch among modes to optimize the usefulness of STF 2.0. An easy access Help memo associated with each of the modes is provided for quick instruction on how to use the available commands in each operation mode. The STF 2.0 operation modes are described in detail below:

* DIRECTORY OPERATING MODE

The "Directory" operating mode is the first to be accessed when entering the Database. This mode provides a quick way of finding and reviewing information in any of the Database files. Upon entering STF 2.0, the User is in the IDENTIFICATION file. The User will find options displayed at the bottom of the screen. The letter or key displayed between { } or <> indicates to the User the letter or key to type. The options include:

{V}IEW: Type **V** to enter the "View" operating mode.

{R}EPORT: Type **R** to enter the "Report" operating mode.

{S}ELECT: Type **S** to select and change files. After S is typed, a list of seven key words, corresponding to the seven STF Database information files, will appear. The User chooses the file to enter by typing the number of the desired file. For example, to select a list of references corresponding to the currently accessed file and chemical at which the cursor is positioned, the User types {S}ELECT then {7}. The User will now be located in file 7 (REFERENCES) at the first full reference citation linked to the file from which the references were accessed (i.e., CHEMICAL CHARACTERISTICS, IMMOBILIZATION, etc.). To view the reference, the User must type {V}IEW.

{H}ELP: Type **H** to enter the HELP memo corresponding to the "Directory" operating mode.

{F}IND: Type **F** to execute a search for a specific chemical. After typing **F**, the User is asked to enter the identification number (IDNUM) of the desired chemical. Identification numbers may be found in the list provided with this manual (Appendix D). For most chemicals, the identification number is the CAS number. The User should enter the complete identification number to ensure that the desired chemical will be accessed. After {F}IND has been executed, the cursor is positioned at the matching chemical. If the chemical is not in STF 2.0, the message "no match found" appears in the bottom left hand corner of the screen. Select the {V}IEW option to access information and data pertaining to that chemical.

FI{L}TER: Type **L** to enter the “Filter” or condition operating mode.

<Arrows>: Indicates the four directional arrows on the cursor pad. The up and down arrows allow the User to scroll the screen up and down. The left and right arrows can be used to scan the IDENTIFICATION or present file records before entering the “View” operating mode. The same information available in the “View” mode is available in the “Directory” mode. By scanning to the right, this information can be viewed.

<PgDn> and <PgUp>: Indicates the PgDn (page down) and PgUp (page up) keys. These keys, in addition to the up and down ARROW keys, allow the User to move through the list of chemicals in the STF Database.

{Q}UIT: Type **Q** to exit the STF Database.

Upon entering the IDENTIFICATION file, the User will normally select the chemical for which information is desired by using the {F}IND option, or the <arrow> commands to search alphabetically. If only a common name, or a portion of the name, of the chemical of interest is known, the User may utilize the “Filter” operating mode to find the desired chemical. A chemical is selected by placing the cursor by that chemical. Once the chemical is selected, the User can access any of the files in the database without changing to a different chemical, or can choose the other commands described above as desired.

* **VIEW OPERATING MODE**

The “**View**” operating mode is entered by typing **V** when the User is in the “Directory” operating mode. The User will find options displayed at the bottom of the screen. These options are:

{M}EMOS: Type **M** to enter a memo field. There must be a memo field displayed on the current screen for this option to be implemented. To exit a memo field, the User should type ESC. The PgUp, PgDn, and directional arrow keys are used to move the cursor within a memo field. There are two types of memo fields used in the STF Database:

- 1) Hidden Memo - Type **M** to view the contents of the memo field.
- 2) Visible Memo - A portion of the memo field appears on the screen. Type **M** to view the rest of the memo field.

Memos are an integral part of STF2.0. Therefore, whenever available, the User should read the information in the memo.

{R}EPORT: Type **R** to enter the “Report” operating mode.

{S}ELECT: Type **S** to select a different data file for the same chemical. After **S** is typed, a list of seven key words corresponding to the seven STF Database information files will

appear. The User chooses the file to enter by typing the appropriate number of the file desired. To access complete references cited as short references in Database files 2-6, the User types {S}ELECT {7}, and the full reference pertaining to the information in the file the User was currently accessing will be displayed. The User will remain in the “View” operating mode.

{N}EXT RECORD, {P}REVIOUS RECORD: Type **N** to view the next record concerning the selected chemical. Type **P** to return to the previous record. If only one record exists, or after the last record for the selected chemical within a specific file, the message “Boundary of Locked IDNUM Encountered” will appear. When this occurs, strike any key to continue.

{U}NLOCK: Type **U** to unlock boundaries to allow the User to leave records for a specific chemical using the **P** or **N** keys, and to move to records for the next chemical in the file. To reset the lock, the User should type **Q** to exit the “View” operating mode, re-select the desired chemical from the “Directory” mode, and type **V** to re-enter the “View” operating mode, and the records for the chemical will again be locked.

The word *LOCKED* appears in the upper right corner of the screen when the boundaries are locked. The IDENTIFICATION file cannot be locked. In all files, if the User is at the top of the file and the {P} option is selected, the message “BEGINNING-OF-FILE ENCOUNTERED, PRESS ANY KEY TO CONTINUE” will appear. If the User is at the bottom of the file and the option {N} is selected, the message “END-OF-FILE ENCOUNTERED, PRESS ANY KEY TO CONTINUE” will appear.

{H}ELP: Type **H** to enter the HELP memo that corresponds to the “View” operating mode.

{Q}UIT: Type **Q** to exit the “View” operating mode. The User will return to the “Directory” operating mode.

<PgDn>, <PgUp>: Use these keys to “turn the pages” in sequence in files that have multiple screens of information for a selected chemical. The files with multiple screens are 2 (CHEMICAL), 3 (IMMOBILIZATION), 4 (TRANSFORMATION), and 5 (TOXICITY).

{F}IND: Type **F** to execute a search for a specific chemical. After typing **F**, the User is asked to enter the identification number (IDNUM) of the desired chemical. Identification numbers may be found in the list provided with this manual (Appendix D). For most chemicals, the identification number is the CAS number for the chemical. The User should enter the complete identification number to ensure that the specific chemical is identified.

* FILTER OPERATING MODE

The “Filter” or condition operating mode allows the User to search or select for a specific chemical or group of chemicals based on information found in STF 2.0 (i.e., physical properties, rates, literature citations, etc.). The “Filter” mode is accessed from the “Directory” or “Report” operating modes by typing FI{L}TER. In the “Report” mode, a printout or file of the information will be generated.

A different set of conditions is available to the User, depending on the information in the file from which the “Filter” mode is entered. For example, if the “Filter” mode is entered while the User is in the TOXICITY file, conditions applicable only to information concerning toxicity will be presented. Once a condition has been specified, it remains in the condition list and is available for use unless it is deleted from the list.

Options available to the User in the “Filter” operation mode, as shown on the bottom of the screen, include:

{A}DD: Type **A** to select conditions upon which the filter/search criteria will be based. A chart with three sections containing options concerning data/information fields, operators and connectors will appear on the screen. The User will be prompted to enter the following information:

- 1) Field number, then strike <RETURN>
- 2) Operator number, then strike <RETURN>
- 3) Desired value for comparison, then strike <RETURN>
- 4) A connector if a more complex condition is desired. If so, repeat steps 1-4. If no connector is desired, strike <RETURN>. When creating a subset of data, the User should usually use the connector option to exclude the value zero from the subset. STF 2.0 utilizes zero as the default number for data fields, even though zeroes do not appear on the screen.
- 5) A custom description (i.e., the User may specify a descriptive name for the condition), then strike <RETURN>. If no custom description is specified, the program defined string that appears in the custom description field becomes the condition name.

{S}ELECT: Type **S** to select an existing condition from the condition list. The User will be prompted to enter the corresponding record number for the specific condition desired. Then strike <RETURN>.

{H}ELP: Type **H** to enter the HELP memo corresponding to the Filter operation mode.

<PgUp>, <PgDn>: Use these keys to scan conditions if multiple screens of conditions exist.

<DELETE>: Strike the DELETE key to remove a condition from the condition list. The User will be prompted to enter the corresponding record number for the specific condition to delete. Then strike <ENTER>.

{Q}UIT: Type **Q** to cancel all current filter conditions and return the User to the point from which the “Filter” operating mode was entered.

When creating a new filter condition, the User is also given two options pertaining to the type of filter to be created. The following prompt appears after the creation of a filter;

Create a global filter Y/N

By typing { Y }, a global filter is created and the flag “GLOBAL FILTER ON” appears in the upper right corner of the screen. By typing { N }, a local filter is created and the flag “FILTER” appears in the same place. The differences between local and global filter applications are summarized below.

Local filter-

A local filter is only valid within the file it was created. For example, if a references-based chemical list is generated by setting a filter in the REFERENCE file and { N } is typed at the prompt, then that list of chemicals can only be accessed in the REFERENCE file and is lost when the User changes files.

Global filter-

A global filter creates a condition-based list according to the file from which it was entered, but unlike a local filter, the list of chemicals can be transferred from file to file. For example, if a identification-based chemical list is generated by setting a filter in the IDENTIFICATION file and { Y } is typed at the prompt, then that list of chemicals can be accessed from any of the seven files.

When the filter mode is re-entered (by typing FI{L}TER) and the flag “GLOBAL FILTER ON” appears in the upper right corner of the screen, the User is prompted with the following options:

{Q}UIT: Allows the User to leave the “Filter” mode

{G}LOBAL: Allows the User to set additional conditions to create a new global filter. These conditions can be set either by selecting a condition already in a STF 2.0 file or by adding new conditions. The new global filter will not supercede the existing filter, but both the new and existing filters will remain for use until deleted.

{S}ELECT: Returns the User to the “Filter” mode where a different filter may be selected or created.

The enhanced “Filter” operating mode in STF 2.0 allows the User to set either file-specific local filters or to create subsets of chemicals that can be carried file to file depending on intended use. For example, when an application calls for dealing only with specific chemicals, those chemicals are put into a subset using the global filter option.

*** REPORT OPERATING MODE**

The “Report” operating mode allows the User to extract data and information contained in STF 2.0. The “Report” mode is accessed from the “Directory” or “View” operating modes by typing {R}EPORT. In the “Report” mode, a printout or file of the information will be generated. Reports are created either by sending the information to the printer or to a DOS text file. A report generated for a printer, especially a laser type printer, requires that the correct command string has been entered in the INSTALL PRINTER introductory option. The default command string is for compressed print and is valid for most dot matrix type printers.

Once the STF 2.0 operating modes have been entered, the only way that the printer command string can be modified is to exit and re-enter the Database. Please refer to the INSTALL PRINTER option in the “GETTING STARTED WITH STF 2.0” section for additional instructions.

Upon entering the “Report” mode, the following options are available:

{1}: Report for current record of the selected chemical in this file.

A report can be prepared for the specific chemical and file that the User is currently accessing. To access this option, type **1**. The User will receive a printout of the information and data for the specific chemical and file being accessed. To terminate printing, the User should strike ALT-C (NOTE: THIS WILL CAUSE THE USER TO EXIT THE STF PROGRAM).

{2}: Report for all records of the selected chemical in this file.

This selection allows the User to print a report of multiple records for the selected chemical in this file. For example, if a particular chemical has three different Immobilization records, this option will print all three files. To access this option, type **2**.

{3}: Report for all records of the filtered group in this file.

A report can be prepared for a subset of chemicals within the current file, which can be created using the “Filter” operating mode. This allows the User to print a report containing information for an entire subset of chemicals. To access this option, type **3**.

{4}: Report for all records of the selected chemical in all files.

A report containing information and data from the seven STF database files for the chemical currently being accessed will be printed. To access this option, type **4**.

{H}: Help

Type **H** to access the HELP memo associated with the “Report” operating mode.

{0}QUIT: Allows the User to leave the “Report” mode

Type **0** to return to the operating mode (“Directory” or “View”) from which the “Report” operating mode was entered.

After options 1, 2, 3, or 4 have been selected, the User is prompted as to the destination of the report file. To send the report to the printer, the filename must be blank. This is accomplished by typing {SPACEBAR}, {ENTER}. To send the report to a file, enter the filename and correct pathway. For example, A:\REPORT.ONE will send the report to the file “REPORT.ONE” to floppy drive a:.

For example, to generate a report for Option 1 for a specific chemical, use the following command sequence:

{R}EPORT (enters “Report” operating mode)

{1} (selects option 1)

<SPACEBAR> (designates the printer as the report destination)

<ENTER> (initiates printing)

Formats of STF 2.0 file reports are given in Appendix E.

A brief tutorial on the use of the STF 2.0 operating modes is presented in Appendix C.

PART II

DESCRIPTION OF THE VIP AND RITZ MODEL EDITORS

The primary purpose of the VIP model editor (VME) and RITZ model editor (RME) is to aid in the creation of input files for the VIP and RITZ models. Input files created in RME and VME are built using three input sources: 1) site specific parameters, entered directly by the user, 2) literature based parameters, entered from STF 2.0, where available, and 3) default parameters, provided as part of the initial setup of new files in RME and VME.

RME and VME are designed to interface with STF 2.0, allowing the User to draw upon studies published in the literature to assess potential transport and fate of chemicals in the vadose zone. Numbers taken from the database are useful for preliminary predictions before in-depth site-specific characterization studies are available. The User should always choose values that are site-specific over those available in STF 2.0.

GETTING STARTED WITH VME AND RME

Once the System Menu has been entered by typing STF at the root directory prompt (typically C:\), the User then types the desired menu option, either { VME } or { RME } editor. Input files created in an editor may be used only in the respective model, since there are significant differences between models.

After a model editor has been selected and entered, the User must enter a filename or leave the field blank to exit. The filename can either be an already existing editor file or a new editor file. The editor requires only the filename to be entered. The file extensions .TOV (“to VIP”) and .TOR (“to RITZ”) are provided as part of all model editor files. The .TOR and .TOV file extensions are used by the program to distinguish between models. If the filename entered is that of an already existing file, that file must be located in the \STFBASE directory, or the editor will not find it. The editor will create a new file with that name. After the filename has been typed, strike <ENTER>. The program now builds different temporary files and indices to allow interaction with STF 2.0. This process may take several minutes.

After the link between STF 2.0 and the model editor has been completed, a list of parameter names appears on the screen. The definitions of each of the parameters and brief instructions as to what types of data should be entered appear as prompt lines immediately below the parameter list. The prompt lines change according to the cursor position on the screen. For complete parameter definitions and other pertinent information regarding these parameters and their use, please refer directly to the RITZ and VIP user’s manuals (Norziger et al., 1988; Stevens et al., 1988; Stevens et al., 1989).

The next step required is that of selecting the chemical(s) of interest. This is done by entering (please refer to the {E}DIT command below for instruction) the STF identification numbers into Line 00 of the parameter list. For each chemical listed (up to twelve), a separate column is initialized for input. Computer runs for different chemicals can be created in the same editor file. At least one chemical identification number must be entered to link the model editor with STF 2.0.

After the chemicals have been selected, additional indices are built by the program. This step also may take several minutes based on the number of chemicals selected and the amount of information contained in STF 2.0 for each chemical. When editing a file that has been previously created, this step is necessary only if the User wishes to change one of the chemicals to be edited.

RME AND VME OPERATING MODE

RME and VME, unlike STF 2.0, have only one operating mode. The screen can be divided into three distinct areas; each area is described in detail below. Where differences between RME and VME occur, separate instructions for each editor will be given under the respective headings.

The first area consists of the top two lines of the screen and is used to orient the User. The model interface is shown in the upper left corner of the screen. It will read either "STF to VIP Interface" or "STF to RITZ Interface." The file in use appears in the upper right corner of the screen. The second line consists of column headings. Line # and DESC----- (description) are fixed, and depending on the number of runs, Title followed by a number (1-12) will appear above the remaining columns as determined by the number of STF identification numbers assigned. For instruction on how to enter identification numbers, the User should refer to the {E}DIT command below.

The second area consists of the parameter list and prompt lines. The parameter list is different for each model. Parameters that are designated by the lucky charm (w) symbol indicate those parameters that can be extracted from STF 2.0. For specific instructions on how to extract values from STF 2.0, the User should refer to the {E}DIT command below. The prompt lines are found directly below the parameter list and correspond to the parameter at which the cursor is found. Brief descriptions of each parameter and information required to correctly enter a parameter, i.e. proper units, etc., are contained in the prompt lines.

The third area consists of the command line at the bottom of the screen. Each command is described in detail below:

{E}DIT: Type {E} to edit a model parameter. Upon typing {E}, the cursor is located in the first "run" or parameter column. At this point, the User has several options:

Site-specific parameters: The User may enter site-specific parameters manually by typing the values directly from the keyboard. Strike <ENTER> when finished.

{F9}: By typing {F9}, the User selects the default parameter provided as part of the initial parameter list in the model editors.

{F10}: {F10} should be typed only when editing parameters that are highlighted by the lucky charm (w) symbol. If values are available in STF 2.0, a pop up table containing a list of these values and conversion information will appear on the screen. Select the desired information using the <arrows> and strike <ENTER>. If the STF field for the desired parameter is empty, the default value is returned and no table appears.

{CTRL-W}: To return to the main menu, strike the {CTRL} and {W} keys simultaneously.

{G}OTO: Type {G} to move directly to a specific point in the parameter list. This can be accomplished using the following options that appear when {G} is typed:

{T}OP: Type {T} to return to the top of the parameter list.

{B}OTTOM: Type {B} to go to the bottom of the parameter list.

{L}INE: Type {L} and enter the line number of the desired parameter, then strike <ENTER>.

<ARROWS>: The up and down arrows are for changing parameters on screen or in tables and for changing columns when editing. The right and left arrows are used to scroll the screen left or right when viewing different columns or to move the cursor when editing.

{C}HANGE FILE: Type {C} to change the file to be edited. The User is then prompted to enter the filename, as before. If the file to be edited is in the \STFBASE directory, then that file will be loaded. If the file is not located in the directory, then a new file by that name will be created for editing. If {C} is typed, but the User decides to remain in the same file, type the filename of the current file being edited.

{H}ELP: Type {H} to review instructions presented in this manual.

{Q}UIT: Type {Q} to exit the model editor. As part of the exiting process, RME and VME will prepare the input files for the RITZ and VIP models. Two different processes are conducted, depending upon which model editor is exited:

RME: The RITZ model can only handle one run at a time. Therefore, when multiple runs have been created in RME, one RITZ input file is created for each run/column in the current file. For example, if the current RME file was named "RUN.TOR" and contained two columns, then upon exiting RME, RITZ input files "RUN1.INP" and "RUN2.INP" are created and stored in the \STFBASE directory.

VME: The VIP model has two different run formats. These run formats are single and multiple. Upon exiting VME, a data file for use in the VIP multiple run format is created. For example, if the current VME file was named "RUN.TOV", upon exiting, VIP input file "RUN.DAT" would be created and stored in the \STFBASE directory. Only one input file is created, even with multiple columns in "RUN.TOV" file.

RUNNING VME AND RME INPUT FILES IN VIP AND RITZ MODELS

Upon exiting VME or RME, the User is transferred by batch file directly into the VIP or RITZ model, respectively. The User must then run or exit the model. Brief instructions on how to run model editor input files in the models are included below. For in depth instruction, the model user's manuals should be consulted (Nofziger et al., 1988; Stevens et al., 1988; Stevens et al., 1989).

VIP: The first prompt presented to the User upon exiting VME asks the User which run format will be used in the model. To run files created in VME, the User must type {2} for multiple run format, even if the input file created has only one column/run. The User is then prompted to enter the filename from which the data will be entered. Normally this would be the current file created upon exiting VME. For example, if the current filename was "RUN.TOR" then the model input file to be entered would be called "RUN.DAT." The third step requires the User to designate the main output file, such as "RUN.OUT." The fourth step prompts the User to characterize the type of output desired. There are six questions that must be answered by typing {Y}ES or {N}O. Please consult the VIP user's manual for specific descriptions of each option. In the fifth and final step, the User must input the number of columns/runs that are found in the input file. The VIP program at this point begins to execute. For in depth explanation of the output generated during execution, please consult the VIP user's manual.

RITZ: Upon exiting RME, the User is taken to an initial introduction or title page of the RITZ model. Strike any key to proceed to the next page. The User is then presented with a default parameter list. To load the input file created in RME, the User must type the function key <F7> and enter the file name. Remember that the RITZ model can only evaluate one run at a time. For example, if the current filename was "RUN.TOR" and the file had two columns/runs, then upon exiting RME, the files "RUN1.INP" and "RUN2.INP" would be created. Type <F7> then select "RUN1.INP" or "RUN2.INP" to be run in RITZ. Once the program has completed execution, the User may re-enter RITZ and select the second model input file for execution. The RITZ also will allow parameters to be changed after the RME input file has been loaded. For further instructions or for an in-depth description of output generated during the execution of RITZ, please consult the RITZ user's manual.

REFERENCES

- Nofziger, D.L., J.R. Williams, and T.E. Short. 1988. Interactive Simulation of the Fate of Hazardous Chemicals During Land Treatment of Oily Wastes: RITZ User's Guide. EPA/600/8-88-001, Robert S. Kerr Environmental Research Laboratory, U.S. Environmental Protection Agency, Ada, OK.
- Stevens, D.K., W.J. Grenney, and Z. Yan. 1988. VIP: A Model for the Evaluation of Hazardous Substances in the Soil, Version 3.0. Civil and Environmental Engineering, Utah State University, Logan, UT 84322-4110.
- Stevens, D.K., W.J. Grenney, Z. Yan, and R.C. Sims. 1989. Sensitive Parameters Evaluation for a Vadose Zone Fate and Transport Model. EPA/600/2-89/039, Robert S. Kerr Environmental Research Laboratory, U.S. Environmental Protection Agency, Ada, OK.

APPENDIX A
INSTALLATION INSTRUCTIONS

APPENDIX A

INSTALLATION INSTRUCTIONS

Soil Transport and Fate Database 2.0 and Model Management System

The diskettes included in the Soil Transport and Fate Database and Model Management System contain STF 2.0, RITZ and VIP model editors, and RITZ and VIP models.

Minimum System Requirements:

- IBM XT Compatible (AT or better is strongly recommended)
- 640 K Ram Memory
- Math Coprocessor (for VIP and RITZ models only)
- Hard Disk with 12.5 Mbytes free
- Supports any display standard (MDA,CGA,EGA)
- Config.sys File must contain the following lines:

FILES = 25
BUFFER = 10

Installation:

To install STF to your hard disk,

1. Insert **STF Disk 1** into disk drive A (or drive B).
2. At the DOS prompt, type **a:install (or b:install)**, then press **Enter**
3. Follow the on screen prompts to complete the installation.

You will be prompted for the drive and directory where STF is to be installed. Press **Enter** to accept the default **C:\STFBASE** or choose a different drive and/or directory. The installation program will create the directory if it does not already exist. The installation program will also ask for permission to modify your config.sys file (if necessary).

A Batch File called STF.BAT will be created in the root directory of the drive you choose for installation. If you have a file named STF.BAT in the root directory, you may want to rename it or it will be overwritten.

Startup:

1. At the DOS prompt type C: (or the drive you choose) then press **Enter**.
2. At the DOS prompt type **CD ** then press **Enter**.
3. At the DOS prompt type **STF** then press **Enter**.

The program is run by typing {STF}, then <ENTER> at the C:\ prompt.

Microsoft Windows and the STF Database:

Currently the STF Database 2.0 is not compatible with Microsoft Windows Version 3.0, and therefore can not be initiated from Windows. If the User has Windows installed, one must "EXIT" Windows before initiating the STF Database.

APPENDIX B
COLOR OPTIONS

APPENDIX B

COLOR OPTIONS

Upon entering the color option menu, the following line appears:

<u>SCREEN</u>	<u>STATUS</u>	<u>WINDOW</u>	<u>PROMPT</u>	<u>HILITE</u>
R+/N,N/W	BU+/N,N/W	R+/N,N/W	GR+/N,N/W	N/W

Where:

SCREEN - Overall screen colors and appearance.

STATUS - The topmost line of the screen.

WINDOW - Lines 1-21 or working area of the screen.

PROMPT - Lines 22-24, the command line.

HILITE - Colors of any highlighted information.

Two default options are provided and are implemented by typing either {MONO} or {COLOR}, depending on the monitor type. If the monitor type is monochrome, there is no need to change the color option. If the monitor is color, type {COLOR} <ENTER> under the SCREEN option. The color default line is shown below:

<u>SCREEN</u>	<u>STATUS</u>	<u>WINDOW</u>	<u>PROMPT</u>	<u>HI-LITE</u>
W+/B,N/W	R/B,N/W	R+/B,N/W	GR+/B,N/W	N/W

The User may use the color chart provided on the following page to change to other color options. The color option syntax must be followed exactly. If syntax is not followed, errors forcing the User out of the STF program are probable. If mistakes are made, re-enter the color option and type {COLOR} or {MONO} to return to default options.

Color Chart

Green	G	Lt Green	G+
Cyan	BG	Lt Cyan	BG+
Red	R	Lt Red	R+
Magenta	BR	Lt Mag	BR+
Brown	GR	Yellow	GR+
Lt Gray	W	White	W+

APPENDIX C
TUTORIAL

APPENDIX C

TUTORIAL

The following tutorial (using the chemical Benzene) is designed to introduce the User to each of the operation modes in STF 2.0. The Keystrokes are found in the "COMMAND" column with comments and descriptions to the right. The tutorial is designed to begin at the System menu. If STF 2.0 has already been entered, the User may exit and begin again or begin at that step corresponding to the present location in the Database.

<u>No</u>	<u>COMMAND</u>	<u>COMMENTS/DESCRIPTION</u>
1	{S}	Enter STF 2.0 from the system menu
2	<ENTER>	Continue to the next page
3	{H}	Enter the Introductory Help Memo
4	<ARROWS> <PG UP> <PG DN>	Browse through the Help Memo
5	<ESC>	Exit memo and return to title page
6	<ENTER>	Continue to the next page
7	<ENTER>	Enter the "Directory" mode (Chemical List)
8	{F}	Execute the Find command
9	{71-43-2} <ENTER>	Identification number for Benzene
10	{V}	Enter "View" mode
11	{S} {2}	Select the CHEMICAL CHARACTERISTICS File
12	<PG DN> <PG DN> <PG DN>	"Turn" the page (total of 4 pages)

13	{M}	Enter Comments Memo on last page of CHEMICAL CHARACTERISTICS
14	<ARROWS> <PG DN> <PG UP>	Browse through Comments Memo
15	<ESC>	Return to the main file
16	{S} {3}	Select the IMMOBILIZATION file
17	<PG DN> <PG UP>	“Turn” the page (total of 3 pages)
18	{S} {4}	Select the TRANSFORMATION/ DEGRADATION file
19	<PG DN> <PG DN>	“Turn” the page (total of 3 pages)
20	{S} {5}	Select the TOXICITY file
21	{M}	Enter Toxicity Data Memo (already appears partially on screen)
22	<ESC>	Exit memo
23	<PG DN>	“Turn” the page (total of 2 pages)
24	{M}	Enter Short Reference and Comments Memo
25	<ESC>	Exit memo
26	{S} {6}	Enter the BIOCONCENTRATION file
27	{M}	Enter Bioconcentration Memo (already appears partially on screen)
28	<ESC>	Exit memo

29	{S} {7}	Enter REFERENCE file; the first reference of the BIOCONCENTRATION file appears, since REFERENCES was entered from BIOCONCENTRATION
30	{N} {P}	N for next record and P for record to move through REFERENCES
31	{S} {7}	Move to the top of the Benzene References (CRC Handbook)
32	{Q}	Enter the “Directory” mode
33	{k } {m }	View data presented in spreadsheet format
34	<PG DN> <PG UP> {k } {m }	Scan References in the “Directory” mode
35	{S} {2}	Select the CHEMICAL CHARACTERISTICS file
36	{k } {m }	Scroll right and view data in the CHEMICAL CHARACTERISTICS file
37	{L}	Enter “Filter” mode in CHEMICAL CHARACTERISTICS file (on screen is the Current Condition List)
38	{S} {1} <ENTER>	Select option 1 from Condition List (1 High M.W. > 400); a list of 11 chemicals appears on screen, starting with Endosulfan and ending with Toxaphene
39	{V}	Enter “View” mode for Endosulfan
40	<PG DN>	“Turn” page, note M.W. = 406.95
41	{Q}	Enter “Directory” mode and recreate list (since the condition selected was not a Global Filter, it must be used only in the CHEMICAL CHARACTERISTICS file)

42	{L}	Enter “Filter” mode
43	<DELETE> {11} <ENTER>	Delete option 11 from Conditions List
44	{A}	Add a new filter to the Conditions List
45	{2} <ENTER>	Designate “Use or Occurrence” as the parameter on which the filter is based
46	{7} <ENTER>	Designate “Contains” as the search criteria
47	{SOLVENT} <ENTER>	“Solvent” is the key word for the search
48	<ENTER>	No connector selected
49	{SOLVENTS}	The custom description that will appear in the Condition List for future use
50	{Y}	Build a Global Filter allowing the User to transfer the list of solvents between files
51	{S} {5}	Enter the TOXICITY file (notice the Global Filter is “on”; indicator in the upper right hand corner of the screen)
52	{L}	Re-enter the “Filter” mode
53	{G}	Allow the User to Filter the current Global set of chemicals further using TOXICITY parameters
54	{A}	Add an additional criteria to current chemical
55	{6} <ENTER>	Designate LD 50 (mg/kg) as the parameter
56	{6} <ENTER>	Designate “< or =” as search criteria

57	{10} <ENTER>	Set 10 (mg/kg) as the limiting value
58	{A}	Enter “and” as the connector (allows for additional criteria for search)
59	{6} <ENTER>	Designate LD 50 (mg/kg) as the parameter
60	{3} <ENTER>	Designate “>” as search criteria
61	{0} <ENTER>	Enter “0” as the lower limit (this stops excludes all blank records from the list)
62	<ENTER>	No connector selected
63	{HIGHLY TOXIC SOLVENTS} <ENTER>	Custom Description that will appear in the Condition List (a list of 3 chemicals is created)
64	{1 }	Place the cursor on Furan
65	{R}	Enter the “Report” mode
66	{1}	Select current chemical for report option
67	{A:TOXSOLV} <ENTER> <ENTER>	Indicate destination for file (a disk must be in drive a:)
68	{N}	No additional conditions are to be set (report is printed to a:)
69	{Q}	Exit STF 2.0

APPENDIX D
STF DATABASE 2.0 CHEMICAL LIST

SOIL TRANSPORT AND FATE DATABASE CHEMICALS

208-96-8	Acenaphthylene	1327-53-3	Arsenic trioxide
75-07-0	Acetaldehyde	115-02-6	Azaserine
104-06-3	Acetanilide, 4'-formyl-, 4'-thiosemicarbazone	7440-39-3	Barium
141-78-6	Acetidin	225-51-4	Benz[c]acridine
67-64-1	Acetone	56-55-3	Benz[a]anthracene
75-05-8	Acetonitrile	71-43-2	Benzene
	Acetophenone	95-53-4	Benzene, 2-amino-1-methyl
81-81-2	3-(alpha-Acetylbenzyl-4- hydroxycoumarin	106-49-0	Benzene, 4-amino-1-methyl
53-96-3	2-Acetylaminofluorene	98-87-3	Benzene, dichloromethyl
591-08-2	1-Acetyl-2-thiourea	98-05-5	Benzenearsonic acid
107-02-8	Acrolein	98-09-9	Benzenesulfonyl chloride
79-06-1	Acrylamide	108-98-5	Benzenethiol
79-10-7	Acrylic acid	92-87-5	Benzidine
107-13-1	Acrylonitrile	205-99-2	Benzo[b]fluoranthene
309-00-2	Aldrin	205-82-3	Benzo[j]fluoranthene
107-18-6	Allyl alcohol	207-08-9	Benzo[k]fluoranthene
92-67-1	4-Aminobiphenyl	50-32-8	Benzo[a]pyrene
50-07-7	6-Amino-1,1a,2,8,8a-hexahydro- 8-(hydroxymethyl)-8a- methoxy-5-methyl-carbamate	106-51-4	p-Benzoquinone
2763-96-4	5-(Aminomethyl)-3-isoxazolol	98-07-7	Benzotrichloride
504-29-0	2-Aminopyridine	100-44-7	Benzyl chloride
61-82-5	Amitrole	7440-41-7	Beryllium
62-53-3	Aniline	111-91-1	Bis(2-chloroethoxy)methane
120-12-7	Anthracene	111-44-4	Bis(2-chloroethyl) ether
7440-36-0	Antimony	494-03-1	N,N-Bis(2-chloroethyl)-2- naphthylamine
140-57-8	Aramite		
53469-21-9	Aroclor 1242 (PCB's)	108-60-1	Bis(2-chloroisopropyl)ether
11097-69-1	Aroclor 1254 (PCB's)	542-88-1	Bis(chloromethyl)ether
11096-82-8	Aroclor 1260 (PCB's)	117-81-7	Bis(2-ethylhexyl) phthalate
7440-38-2	Arsenic	598-31-2	Bromoacetone
7778-39-4	Arsenic acid	75-27-4	Bromodichloromethane
1303-28-2	Arsenic pentoxide	74-83-9	Bromomethane
		357-57-3	Brucine
		1338-23-4	2-Butanone peroxide
		71-36-3	n-Butyl alcohol
		85-68-7	Butyl benzyl phthalate
		88-85-7	2-sec-Butyl-4,6-dinitrophenol

7440-43-9	Cadmium	20830-81-3	Daunomycin
592-01-8	Calcium cyanide	72-54-8	DDD
75-15-0	Carbon disulfide	72-55-9	DDE
75-87-6	Chloral	50-29-3	DDT
305-03-3	Chlorambucil	2303-16-4	Diallate
57-74-9	Chlordane	226-36-8	Dibenz[a,h]acridine
107-20-0	Chloroacetaldehyde	224-42-0	Dibenz[a,j]acridine
106-47-8	p-Chloroaniline	53-70-3	Dibenz[a,h]anthracene
108-90-7	Chlorobenzene	194-59-2	7H-Dibenzo[c,g]carbazole
510-15-6	Chlorobenzilate	192-65-4	Dibenzo[a,e]pyrene
126-99-8	2-Chloro-1,3-butadiene	189-64-0	Dibenzo[a,h]pyrene
59-50-7	p-Chloro-m-cresol	189-55-9	Dibenzo[a,i]pyrene
124-48-1	Chlorodibromomethane	96-12-8	1,2-Dibromo-3-chloropropane
106-89-8	1-Chloro-2,3-epoxypropane	106-93-4	1,2-Dibromoethane
110-75-8	2-Chloroethyl vinyl ether	74-95-3	Dibromomethane
67-66-3	Chloroform	84-74-2	Di-n-butyl phthalate
74-87-3	Chloromethane	95-50-1	o-Dichlorobenzene
107-30-2	Chloromethyl methyl ether	541-73-1	m-Dichlorobenzene
91-58-7	2-Chloronaphthalene	106-46-7	p-Dichlorobenzene
95-57-8	2-Chlorophenol	91-94-1	3,3'-Dichlorobenzidine
5344-82-1	1-(o-Chlorophenyl)thiourea	764-41-0	1,4-Dichloro-2-butene
107-05-1	3-Chloropropene	75-71-8	Dichlorodifluoromethane
542-76-7	3-Chloropropionitrile	75-34-3	1,1-Dichloroethane
3165-93-3	4-Chloro-o-toluidine, hydrochloride	107-06-2	1,2-Dichloroethane
7440-47-3	Chromium	25323-30-2	Dichloroethylene
218-01-9	Chrysene	75-35-4	1,1-Dichloroethylene
8007-45-2	Coal tar	540-59-0	1,2-Dichloroethylene
8001-58-9	Creosote	156-60-5	1,2-trans-Dichloroethylene
1319-77-3	Cresols	75-09-2	Dichloromethane
108-39-4	m-Cresol	120-83-2	2,4-Dichlorophenol
95-48-7	o-Cresol	87-65-0	2,6-Dichlorophenol
106-44-5	p-Cresol	94-75-7	2,4-Dichlorophenoxyacetic acid
4170-30-3	Crotonaldehyde	696-28-6	Dichlorophenylarsine
57-12-5	Cyanide	78-99-9	1,1-Dichloropropane
506-68-3	Cyanogen bromide	78-87-5	1,2-Dichloropropane
506-77-4	Cyanogen chloride	142-28-9	1,3-Dichloropropane
14901-08-7	Cycasin	96-23-1	1,3-Dichloro-2-propanol
110-82-7	Cyclohexane	616-23-9	2,3-Dichloro-1-propanol
108-94-1	Cyclohexanone	563-54-2	1,2-Dichloropropene
131-89-5	2-Cyclohexyl-4,6-dinitrophenol	542-75-6	1,3-Dichloropropene
50-18-0	Cyclophosphamide	60-57-1	Dieldrin
		1464-53-5	1,2:3,4-Diepoxybutane

692-42-2	Diethylarsine	621-64-7	Di-n-propylnitrosamine
1615-80-1	N,N'-Diethylhydrazine	298-04-4	Disulfoton
3288-58-2	O,O-Diethyl S-methyl ester of phosphorodithioc acid	541-53-7	2,4-Dithiobiuret
311-45-5	O,O-Diethylphosphoric acid, O-p-nitrophenyl ester	115-29-7	Endosulfan
84-66-2	Diethyl phthalate	72-20-8	Endrin
297-97-2	O,O-Diethyl O-2-pyrazinyl phorodithioate	140-88-5	Ethyl acrylate
56-53-1	Diethylstilbesterol	51-79-6	Ethyl carbamate
94-58-6	Dihydrosafrole	107-12-0	Ethyl cyanide
51-43-4	3,4-Dihydroxy-alpha- (methylamino) methyl benzyl alcohol	110-80-5	Ethylene glycol monoethyl ether
55-91-5	Diisopropylfluorophosphate	75-21-8	Ethylene oxide
60-51-5	Dimethoate	111-54-6	Ethylenebisdithiocarbamic acid
119-90-4	3,3'-Dimethoxybenzidine	151-56-4	Ethyleneimine
60-11-7	p-Dimethylaminoazobenzene	96-45-7	Ethylenethiourea
57-97-6	7,12-dimethylbenz[a]anthracene	97-63-2	Ethyl methacrylate
119-93-7	3,3'-Dimethylbenzidine	62-50-0	Ethyl methanesulfonate
80-15-9	alpha,alpha-Dimethyl- b enzyhydro peroxide	206-44-0	Fluoranthene
79-44-7	Dimethylcarbomayl chloride	86-73-7	Fluorene
57-14-7	1,1-Dimethylhydrazine	640-19-7	2-Fluoroacetamide
540-73-8	1,2-Dimethylhydrazine	144-49-0	Fluoroacetic acid
39196-18-4	3,3'-Dimethyl-1-(methylthio)- 2-buta none, O-[(methylamino) carbonyl]oxme	62-74-8	Fluoroacetic acid, sodium salt
122-09-8	alpha,alpha-Dimethyl- phenethylamine	50-00-0	Formaldehyde
105-67-9	2,4-Dimethylphenol	64-18-6	Formic acid
131-11-3	Dimethyl phthalate	110-00-9	Furan
77-78-1	Dimethyl sulfate	98-01-1	2-Furaldehyde
99-65-0	Dinitrobenzene	765-34-4	Glycidaldehyde
534-52-1	4,6-Dinitro-o-cresol	76-44-8	Heptachlor
51-28-5	2,4-Dinitrophenol	1024-57-3	Heptachlor epoxide
121-14-2	2,4-Dinitrotoluene	118-74-1	Hexachlorobenzene
606-20-2	2,6-Dinitrotoluene	35065-27-1	2,2',4,4',5,5'-Hexachlorobiphenyl
117-84-0	Di-n-octyl phthalate	87-68-3	Hexachlorobutadiene
123-91-1	1,4-Dioxane	319-84-6	1,2,3,4,5,6-Hexachlorocyclo- hexane, alpha isomer
122-39-4	Diphenylamine	58-89-9	1,2,3,4,5,6-Hexachlorocyclo- hexane, gamma isomer
122-66-7	1,2-Diphenylhydrazine	77-47-4	Hexachlorocyclopentadiene
142-84-7	Dipropylamine	39227-28-6	1,2,3,4,7,8-Hexachlorodibenzo- p-dioxin
		9999-00-2	Hexachlorodibenzofurans
		67-72-1	Hexachloroethane
		465-73-6	1,2,3,4,10,10-Hexachloro- 1,4,4a,5,8, 8a-hexahydro- 1,4:5,8-endo,endo- dimethanonaphthalene

70-30-4	Hexachlorophene	298-00-0	Methyl parathion
1888-71-7	Hexachloropropene	56-04-2	Methylthiouracil
302-01-2	Hydrazine	91-20-3	Naphthalene
74-90-8	Hydrocyanic acid	130-15-4	1,4-Naphthoquinone
7783-06-4	Hydrogen sulfide	134-32-7	1-Naphthylamine
75-60-5	Hydroxydimethylarsine oxide	91-59-8	2-Naphthylamine
193-39-5	Indeno(1,2,3-cd)pyrene	86-88-4	1-Naphthyl-2-thiourea
74-88-4	Iodomethane	7440-02-0	Nickel
624-83-9	Isocyanic acid, methyl ester	13463-39-3	Nickel carbonyl
78-83-1	Isobutyl alcohol	54-11-5	Nicotine
120-58-1	Isosafrole	10102-43-9	Nitric oxide
143-50-0	Kepone	98-95-3	Nitrobenzene
303-34-4	Lasiocarpine	55-63-0	Nitroglycerine
7439-92-1	Lead	100-01-6	p-Nitroaniline
301-04-2	Lead acetate	100-02-7	4-Nitrophenol
108-31-6	Maleic anhydride	79-46-9	2-Nitropropane
123-33-1	Maleic hydrazide	924-16-3	N-Nitrosodi-n-butylamine
109-77-3	Malonitrile	1116-54-7	N-Nitrosodiethanolamine
148-82-3	Melphalan	55-18-5	N-Nitrosodiethylamine
7439-97-6	Mercury	62-75-9	N-Nitrosodimethylamine
126-98-7	Methacrylonitrile	759-73-9	N-Nitroso-N-ethylurea
74-93-1	Methanethiol	10595-95-6	N-Nitrosomethylethylamine
67-56-1	Methanol	684-93-5	N-Nitroso-N-methylurea
91-80-5	Methapyrilene	615-53-2	N-Nitroso-N-methylurethane
16752-77-5	Metholmyl	4549-40-0	N-Nitrosomethylvinylamine
72-43-5	Methoxychlor	59-89-2	N-Nitrosomorpholine
75-55-8	2-Methylaziridine	100-75-4	N-Nitrosopiperidine
79-22-1	Methyl chlorocarbonate	930-55-2	Nitrosopyrrolidine
56-49-5	3-Methylcholanthrene	99-55-8	5-Nitro-o-toluidine
101-14-4	4,4'-Methylenebis (2-chloroaniline)	152-16-9	Octamethylpyrophosphoramide
78-93-3	Methyl ethyl ketone	145-73-3	7-Oxabicyclo[2,2,1]heptane-2,3- dicarboxylic acid
60-34-4	Methyl hydrazine	123-63-7	Paraldehyde
108-10-1	Methyl isobutyl ketone	56-38-2	Parathion
75-86-5	2-Methylactonitrile	608-93-5	Pentachlorobenzene
80-62-6	Methyl methacrylate	9999-00-1	1,2,3,7,8-Pentachlorodibenzo-p- dioxin
66-27-3	Methyl methanesulfonate	9999-00-4	Pentachlorodibenzofurans
116-06-3	2-Methyl-2-(methylthio) propional dehyde-o- (methylcarbonyl) oxime	76-01-7	Pentachloroethane
90-12-0	1-Methylnaphthalene	82-68-8	Pentachloronitrobenzene
70-25-7	N-Methyl-N'-nitro- N-nitrosoguanidine	87-86-5	Pentachlorophenol
		504-60-9	1,3-Pentadiene
		62-44-2	Phenacetin

85-01-8	Phenanthrene	9999-00-3	1,2,3,7-Tetrachlorodibenzo-
108-95-2	Phenol		p-dioxin
108-45-2	m-Phenylenediamine	33423-92-6	1,3,6,8-Tetrachlorodibenzo-
95-54-5	o-Phenylenediamine		p-dioxin
106-50-3	p-Phenylenediamine	1746-01-6	2,3,7,8-Tetrachlorodibenzo-
62-38-4	Phenylmercury acetate		p-dioxin
103-85-5	N-Phenylthiourea	51207-31-9	2,3,7,8-Tetrachlorodibenzofuran
75-44-5	Phosgene	630-20-6	1,1,1,2-Tetrachloroethane
7803-51-2	Phosphine	79-34-5	1,1,2,2-Tetrachloroethane
298-02-2	Phosphorodithioic acid, O,O-diethyl	127-18-4	Tetrachloroethene
	S-[(ethylthio)methyl] ester	56-23-5	Tetrachloromethane
52-85-7	Phosphorothioic acid, O,O-dimethyl	58-90-2	2,3,4,6-Tetrachlorophenol
	O-[p((dimethylamino)sulfonyl) phenyl] ester	78-00-2	Tetraethyl lead
		107-49-3	Tetraethylpyrophosphate
88-99-3	Phthalic acid	109-99-9	Tetrahydrofuran
85-44-9	Phthalic anhydride	509-14-8	Tetranitromethane
109-06-8	2-Picoline	7440-28-0	Thallium
1336-36-3	Polychlorinated biphenyls	10102-45-1	Thallium (I) nitrate
151-50-8	Potassium cyanide	62-55-5	Thioacetamide
506-61-6	Potassium silver cyanide	79-19-6	Thiosemicarbazide
23950-58-5	Pronamide	62-56-6	Thiourea
1120-71-4	1,3-Propane sultone	137-26-8	Thiuram
107-10-8	n-Propylamine	108-88-3	Toluene
107-19-7	2-Propyn-1-ol	95-80-7	2,4-Toluenediamine
129-00-0	Pyrene	584-84-9	Toluene diisocyanate
110-86-1	Pyridine	636-21-5	o-Toluidine hydrochloride
504-24-5	Pyridine, 4-amino-	8001-35-2	Toxaphene
50-55-5	Reserpine	75-25-2	Tribromomethane
108-46-3	Resorcinol	120-82-1	1,2,4-Trichlorobenzene
81-07-2	Saccharin	71-55-6	1,1,1-Trichloroethane
94-59-7	Safrole	79-00-5	1,1,2-Trichloroethane
7782-49-2	Selenium	79-01-6	Trichloroethene
7488-56-4	Selenium sulfide	9999-00-5	Trichloromonofluoroethane
630-10-4	Selenourea	75-69-4	Trichloromonofluoromethane
7440-22-4	Silver	95-95-4	2,4,5-Trichlorophenol
143-33-9	Sodium cyanide	88-06-2	2,4,6-Trichlorophenol
18883-66-4	Streptozotocin	93-76-5	2,4,5-Trichlorophenoxyacetic acid
57-24-9	Strychnine	93-72-1	2,4,5-Trichlorophenoxy- propionic acid
95-94-3	1,2,4,5-Tetrachlorobenzene	7789-89-1	1,1,1-Trichloropropane
30746-58-8	1,2,3,4-Tetrachlorodibenzo- p-dioxin	598-77-6	1,1,2-Trichloropropane

3175-23-3	1,2,2-Trichloropropane
96-18-4	1,2,3-Trichloropropane
76-13-1	1,1,2-Trichloro-1,2,2-trifluoroethane
99-35-4	sym-Trinitrobenzene
52-24-4	Tris(1-aziridinyl)phosphine sulfide
126-72-7	Tris(2,3-dibromopropyl)phosphate
72-57-1	Trypan blue
66-75-1	Uracil mustard
1314-62-1	Vanadium pentoxide
75-01-4	Vinyl chloride
108-38-3	m-Xylene
95-47-6	o-Xylene
106-42-3	p-Xylene
1314-84-7	Zinc phosphide

APPENDIX E

STF 2.0 FILES AND ASSOCIATED INFORMATION

Page - 1 Soil Transport and Fate Database
Identification Information

ID Number:

STF Name / Common Names

Page - 1 Soil Transport and Fate Data Base
Chemical Characteristics

ID Number: Type:

STF Name:

Use or Occurrence:

Formula:

Short Reference:

Molecular Mass (g/mole):

MS Molecular Mass (g/mole):

Vapor Pressure (torr): E
 E
 E

Viscosity (g/cm-s): E
 E
 E

Specific Gravity:

Melting Point: (x°C):

Boiling Point: (x°C):

Short Reference:

Henry's Law Constant: E
 (dimensionless) E

Diffusivity Coef., Air: E
 (sp. cm/s) E

Diffusivity Coef., Water: E
 (sp. cm/s) E

Gibb's Free Energy: E
 (kcal/mole) E

Log Octanol-Water:

Page - 2 Soil Transport and Fate Data Base
Chemical Characteristics

Short Reference:

Acid Dissociation Constant:	E
(pka)	E

Solubility in Water (mg/l):	E
	E

Detection Limit in Aqueous Medium:

EPA Guidance Concentration:

Air (ug/m³)

Water (ug/l)

Soil (ug/g)

Medium:

Analytical Method:

Short Reference:

Short Reference and Comments Memo:

**Page - 1 Soil Transport and Fate Data Base
Immobilization**

ID Number: Type:

STF Name:

Soil Type and Conditions

Soil Name: Texture:

pH Range: - Average Temperature: (°C)

Average Moisture Content:

SOIL PROPERTIES

Permeability: (cm/d) Cation Exchange Capacity: (cmol/kg)

Organic Carbon (%): Saturated Water Content (fraction):

Saturated Hydraulic Conductivity: Porosity:

Bulk Density of Soil: (g/cm³) Particle Effective Size: (mm)

WASTE PROPERTIES

Constituent Concentration (g/m³):

Mass Fraction of Oil: Mass Fraction of Water:

Density of Oil (g/cm³): Viscosity of Oil (cp):

log Ko: log Kh: log Kd:

Kf 1/n R² Kf 1/n R² Kf 1/n R²

Low High Short References/Comments:

log Ko:

log Kh:

log Kd:

log Koc:

log Koa:

log Ksa:

Page - 2 Soil Transport and Fate Data Base
Immobilization

Other Constituent Concentrations Memo

Comments Memo:

Page - 1 Soil Transport and Fate Data Base
Transformation/Degradation

ID Number: Type:

STF Name:

Soil Type and Conditions

Soil Name:

Texture:

pH Range: - Average Temperature: (°C)

Average Moisture Content:

SOIL PROPERTIES

Permeability: (cm/d) Cation Exchange Capacity: (cmol/kg)

Organic Carbon (%): Saturated Water Content (fraction):

Saturated Hydraulic Conductivity: Porosity:

Bulk Density of Soil: (g/cm³) Particle Effective Size: (mm)

WASTE PROPERTIES

Constituent Concentration (g/m³):

Mass Fraction of Oil: Mass Fraction of Water:
Density of Oil (g/cm³): Viscosity of Oil (cp):

Co (mg/kg) k (1/day) t 1/2 (days) R²

 Low High Short Reference/Comments:
k (1/day):

t 1/2 (days):

**Page - 2 Soil Transport and Fate Data Base
Transformation/Degradation**

Other Constituent Concentrations Memo:

Experimental Description, Transformation Products and/or Short Reference and Comments Memo:

**Page - 1 Soil Transport and Fate Data Base
Toxicity Data**

ID Number: Type:

STF Name:

Carcinogenic Risk

Units: Short Reference/Comments:

Reference Dose:

Risk Specific Dose:

Toxicity Data Memo:

LC 50: (mg/l) Organism:
 (mg/l)
 (mg/l)

LD 50: (mg/kg) Route: Animal:
 (mg/kg)
 (mg/kg)

EC 50: Units: Organism:

Ames Salmonella typhimurium Assay:

Mutagenic Ratio: Mutagenic Dose:

Scale:

Short Reference and Comments Memo:

Page - 1 Soil Transport and Fate Data Base
Bioconcentration

ID Number: Type:

STF Name:

Short Reference:

Log Kow:

Log Bioconcentration:

Bioconcentration Data & Short Reference Memo

Page - 1 Soil Transport and Fate Data Base
References Data

Id Number	Short Reference	Ref. Type
-----------	-----------------	-----------

APPENDIX F

LIST OF JOURNALS, DOCUMENTS, AND REPORTS CITED

Acta Agronomica Acadamiae	Chemical Data for Predicting the Fate of Organic Compounds in Water, Volume 2
Scientiarium Hungaricae	Chemical Engineers' Handbook, 5th ed.
Advanced Drug Research	Chemical Mutagens, Vol. 8
Agricultural and Food Chemistry	Chemical Review
Annals of Applied Biology	Chemosphere
Applied and Environmental Microbiology	Choosing a Process for Chloride Removal
Aquatic Toxicology	Contaminated Surface Soils in Place Treatment Techniques
Archives of Environmental Contamination Toxicology	CRC Critical Reviews in Environmental Control
Archives of Toxicology	CRC Critical Reviews in Microbiology
ASTM Technical Publication #707	Cytobios
Biochemistry and Biophysics Research Communications	Development of Predictive Models for Xenobiotoc Bioaccumulation in Terrestrial Ecosystems
Biochemical Journal	Developmental Toxicology and Environmental Science
Biodegradation and Bioaccumulation Test on Chemical Substances OECD Tokyo Meeting Reference Book TSU-No.3	Drinking Water and Health
Botanic Marina	Deutsche Gewasser Kundliche Miteilungen
Bulletin of the Japanese Society of Scientific Fisheries	Dynamic Exposure and Hazardous Assessment of Toxic Chemicals
Bulletin, Entomological Society of Egypt. Economic Series	Ecotoxicology and Environmental Safety
Bulletin of Environmental Contamination and Toxicology	Elaboration of Sediment Normalization Theory for Nonpolar Hydrophobic Organic Chemicals
Bulletin of the National Institute of Hydrological Science	Environmental and Geological Water Science
C. & S. Mar. Solvents Guide	Environmental Health Perspectives
Canadian Journal of Agricultural Science	Environmental Impact of Nonpoint Source Pollution
Canadian Journal of Fisheries and Aquatic Sciences	Environment International
Canadian Journal of Microbiology	Environmental Mutagenicity
Cancer Research	Environmental Pollution
Chemistry and Biology	Environmental Progress
Chemical Data Bases for the Multimedia Environmental Pollutant Assessment System (MEPAS)	

Environmental Science Services Corporation	Health and Ecological Assessment of Polynuclear Aromatic Hydrocarbons
Environmental Science and Technology	Horticultural Science
Environmental Toxicology and Chemistry	Hydrologie
ERT--The Land Treatability of Creosote/ Pentachlorophenol Wastes	IARC Monographs
European Journal of Applied Microbiology and Biotechnology	Indian Oil Seeds Journal
Fate of Lindane in the Aquatic Environment	Industrial Hygiene and Toxicology, 3rd ed.
Fish Bulletin National Marine Fish Service	Industrial Effluent Standards for Toxic Pollutants: Proceedings 36th Industrial Waste Conference
Food and Chemical Toxicology	International Priority Pollutants
Food Contaminants & Aqueous Wastes	Japanese Journal of Industrial Health
Food and Cosmetics Toxicology	Journal of Biological Chemistry
Foreign Compound Metabolism in Mammals	Journal of Bulletin Philosophical Biochemical Society
GE Material Safety Data Sheet #366	Journal of Chromatography
Geochimica et Cosmochimica Acta	Journal of Environmental Pathology and Toxicology
Glassware Crops Research Institute Report	Journal of the Fisheries Research Board of Canada
Groundwater Chemicals Desk Reference	Journal of General Microbiology
Handbook of Acute Toxicity of Chemicals to Fish and Aquatic Invertebrates	Journal of Investigative Dermatology
Handbook of Chemical Property Estimation	Journal of Physical Chemical Reference Data
Handbook of Chemistry and Physics, 1990, 70th ed.	Journal of Applied Ecology
Handbook of Chemistry and Physics, 1987, 70th ed.	Journal of Contaminant Hydrology
Handbook of Environmental Data on Organic Chemicals, 2nd ed.	Journal of Economic Entomology
Handbook of Environmental Fate and Exposure Data for Organic Chemicals, Vol. I	Journal of Environmental Quality
Hazardous Material Control Research Institute (HMCRI)	Journal of Environmental Science and Technology
Hazardous Waste and Hazardous Materials	Journal of Physical Chemistry
Hazardous Waste Land Treatment	Journal of Science and the Total Environment
	Journal of Soil Science

Journal of the Environmental Engineering Division--ASCE	OECD Tokyo Meeting Reference Book
Journal of the National Cancer Institute	Pesticide Manual, 6th ed.
Journal of the Science of Food and Agriculture	Pesticide Science
Journal of the Water Pollution Control Federation	Photochemistry and Photobiology
Kirk-Othmer Encyclopedia of Chemical Technology, 3rd ed.	Phytopathology
Log P Database	Polycyclic Aromatic Hydrocarbons in the Aqueous Environment
Manual of Treatment Processes	Proceedings of the Royal Society of London, Ser. B
Marine Environmental Research	QSAR in Toxicology and Xenobiochemistry
Marine Pollution Bulletin	Residue Reviews
Medchem Project Issue No. 26	Retention and Transformation of Pesticides and Phosphorus in Soil-Water Systems
Medchem Project Issue No. 19	Reviews of Environmental Contamination and Toxicology
Merck Index, 11th ed.	Sango Igaku
Merck Index, 10th ed.	Science
Merck Index, 8th ed.	Science of the Total Environment
Metabolism of Pesticides	SERA Economic Biology
Mutation Research	Soil Biology and Biochemistry
Nature	Soil Science Society of America Proceedings
NIH/EPA 1985 OHM/TADS	Soil Science Society of America Journal
NIOSH RTECS online file	Solvents Guide
NIOSH RTECS 1981-82 Vols I-III	Substituent Constants for Correlation Analysis in Chemistry and Biology
NRCC (National Research Council Canada)	Technical Bulletin/NTP
Nuclear and Chemical Waste Management	Textile Chemist and Colorist
NUREG/CR-089	Teratogenesis, Carcinogenesis, Mutagenesis
Oak Ridge National Laboratory/ EIS-155/V1/1979	The Effect of Sediment Suspension on Adsorption and Fate of Kepone
Oak Ridge National Laboratory/6451	
Oceanic Atmosphere	

The Land Treatability of Appendix VII Constituents Present in Petroleum Refinery Wastes	USEPA 600/6-86-003b
	USEPA 600/6-88-001
The Journal of Chemical and Engineering Data	USEPA 600/7-78-074
	USEPA 600/9-79-012
The Pesticide Book	USEPA 68-01-6030
The Soil Chemistry of Hazardous Materials	USEPA Report NTIS PB278-269
Toxicity Assessment	USEPA HEAST--Health Effects Assessment Summary Tables
Toxicological Epidemiological Mechanisms Toxicology	USEPA--Potential Terrestrial Impacts of Contaminated Soil
Toxicology Letter	
USAF--The Installation Restoration Program Toxicology Guide, Volumes 2 and 3	Waste Management and Research
	Water, Air, and Soil Pollution
USEPA CR-811498010	Water Research
USEPA/ECAO--Health and Environmental Effects Profile, Cresols ECAO-CIN-P138	Water Resources
USEPA SW 846--Test Methods for Evaluating Solid Waste	Zeitschrift fur Wasser-und Abwasser Forschung
USEPA SW 874--Hazardous Waste Land Treatment	
USEPA 440/4-79-029b	
USEPA 530/SW-89-031	
USEPA 540/2-84-003b	
USEPA 560/2-76-010	
USEPA 560/5-77-005	
USEPA 560/11-80-006	
USEPA 600/3-80-041	
USEPA 600/3-82-060	
USEPA 600/4-82-057	
USEPA 600/6-84-009	
USEPA 600/6-84-011	
USEPA 600/6-86-003a	