APPENDIX A

Models-3 Directory Tree

The Models-3 tree is usually housed in D:\models3. This may be configured to be a different directory during installation. The name must not contain any capital letters. This top-level directory is identified by the environment variable %M3HOME%. The five main sections of the tree are:

- *datasets* %M3DATA%: Inputs and outputs to studies reside in .\studies and .\nostudies. This will be the area that is prone to the most growth as far as disk space is concerned.
- *exec* %M3HOME%\exec: Executables that have been tagged as "official" are placed in this area. The users have permissions to modify this area. There will be subdirectories for models and each hardware platform.
- framework %M3HOME%\framework: Programs that allow the users to run the suite of tools and models are stored in this directory along with the database and Orbix configuration files. Users have privileges to modify the database files only.
- *models* %M3HOME\models: Scientific models are stored in this area. The conforming models are written in FORTRAN and must be compiled before they are run. The users in group "models3" have permissions to modify this area.
- *tools* %M3HOME%\tools: Third-party tools, freeware, and scripts that kick off commercial executables from the framework. The users do not have permissions to change the contents of this directory.

The top two levels of the tree are as follows:

```
datasets:
nostudies\ studies\
exec:
protected\
framework:
bin\ config\ db\ installdb\ lib\ templates\
models:
CCTM\ ICON\ MCIP\ LUPROC\ MECH\ include\
ECIP\ BCON\ JPROC\ PROCAN\ PDM\ SMOKETOOL\
```

tools:

The complete listing of all files that were used to create the framework and models code are in %M3HOME%\framework\installdb\BillOfMaterials.txt. It also contains a listing of every file included on the latest installation tape.

APPENDIX B

Models-3 Environment Variables

The following environment variables are used by the Models-3 system. They are set in the m3env.bat script.

Environment Variable	Value	Description
Models-3 Directorie	25	
M3HOME	usually D:\models3	base directory where software is installed
M3FRAME	%M3HOME%\framework	framework files and database
	%M3HOME%\datasets	datasets
M3EXEC	%M3HOME%\exec	executables - compiled models
M3TOOLS	%M3HOME%\tools	tools to use - do not compile these
M3MODEL	%M3HOME%\models	source code for scientific models
M3FBIN	%M3FRAME%\bin	framework binary executables
M3FLIB	%M3FRAME%\lib	framework libraries
M3FSRC	%M3FRAME%\src	framework source - empty for most sites
M3FINC	%M3FRAME%\inc	framework include files - empty for most
		sites
M3FDBPATH	%M3FRAME%\db	framework database files
M3FDBNAME	%M3FDBPATH%\model	main framework database
	s3.db	
M3MCTM	%M3MODEL%\CCTM	CTM model (chemistry)
M3MSTOOL	%M3MODEL%\smoketo	Smoke Tool source code and libraries
	ol	
M3TEMP	usually it is /tmp or	holds temporary files
	C:\TEMP	
Other		
M3SITE	(system dependent)	unique site name
M3HOST	(system dependent)	host name, including domain name
M3FMHOST	(system dependent)	host name where File Migrator is running
M3USERHOME	(system dependent)	the user's home directory

Table B-1. Models-3 Framework Environment Variables

APPENDIX C

Selected Dataset Details

The following table describes selected datasets under the nostudies area. Acronyms may be found in Appendix B of User Manual.

Key: M is Main. Main datasets are distributed with the Models-3 Software.S is Supplemental. Supplemental datasets are available separately from EPA and/or NTIS.

TABLE C-1. Selected Datasets Under Nostudies		
Dataset Name	File Location	Tape
BC profile data for BCON	%M3DATA%\nostudies\bcon\bc_profile_v5.dat	M
IC profile data for ICON	%M3DATA%\nostudies\bcon\ic_profile_v5.dat	M
Land-use data for LUPROC	%M3DATA%\nostudies\bcon\mm5_soil_data	M
Hourly ozone measurements July 6-10, 1995 (SAS)	%M3DATA%\nostudies\ozone\o3_dev.ssd01	M
Hourly ozone measurements July 11-15, 1995 (SAS)	%M3DATA%\nostudies\ozone\o3_evl.ssd01	М
Site locations for all available monitoring stations for July 6-15, 1995 (SAS)	%M3DATA%\nostudies\ozone\site.ssd01	M
Hourly ozone measurements from NARSTO for 1995	%M3DATA%\nostudies\narsto_ne_1995\ AME07AI1.1HR	M
Description of NARSTO Data	%M3DATA%\nostudies\narsto_ne_1995\ narsto_ne_readme95.txt	M
Extra-terrestrial irradiance values for JPROC	%M3DATA%\nostudies\phot\ETirradiance.dat	M
Vertical Profiles data for JPROC	%M3DATA%\nostudies\phot\PROFILES.dat	M


TABLE	C-1. Selected Datasets Under Nostudies	
Dataset Name	File Location	Tape
O2 absorption cross section data for JPROC	%M3DATA%\nostudies\phot\O2_NASA94	M
O2 absorption cross section data for JPROC	%M3DATA%\nostudies\phot\O2_RADM88	M
O3 Photolysis to O1D for JPROC	%M3DATA%\nostudies\phot\O3O1D_NASA9 4	M
O3 Photolysis to O1D for JPROC	%M3DATA%\nostudies\phot\O3O1D_RADM8 8	M
O3 Photolysis to O1D for JPROC	%M3DATA%\nostudies\phot\O3O1D_CBIV88	M
O3 Photolysis to O3P for JPROC	%M3DATA%\nostudies\phot\O3O3P_RADM8 8	M
O3 Photolysis to O3P for JPROC	%M3DATA%\nostudies\phot\O3O3P_NASA94	M
Nitrogen Dioxide Photolysis for JPROC	%M3DATA%\nostudies\phot\NO2_RADM88	M
Nitrogen Dioxide Photolysis for JPROC	%M3DATA%\nostudies\phot\NO2_CBIV88	M
Nitrogen Dioxide Photolysis for JPROC	%M3DATA%\nostudies\phot\NO2_NASA94	M
Nitrate Photolysis to NO for JPROC	%M3DATA%\nostudies\phot\NO3NO_RADM 88	M
Nitrate Photolysis to NO for JPROC	%M3DATA%\nostudies\phot\NO3NO_NASA-94	M
Nitrate Photolysis to NO2 for JPROC	%M3DATA%\nostudies\phot\ NO3NO2_RADM88	M
Nitrate Photolysis to NO2 for JPROC	%M3DATA%\nostudies\phot\ NO3NO2_NASA94	M
Nitrous Acid Photolysis for JPROC	%M3DATA%\nostudies\phot\HONO_RADM8 8	M

TABLE	CC-1. Selected Datasets Under Nostudies	
Dataset Name	File Location	Tape
Nitrous Acid Photolysis for JPROC	%M3DATA%\nostudies\phot\HONO_NASA94	M
Nitric Acid Photolysis for JPROC	%M3DATA%\nostudies\phot\ HNO3_RADM88	M
Nitric Acid Photolysis for JPROC	%M3DATA%\nostudies\phot\ HNO3_NASA94	M
Pernitric Acid Photolysis for JPROC	%M3DATA%\nostudies\phot\HNO4_RADM88	M
Pernitric Acid Photolysis for JPROC	%M3DATA%\nostudies\phot\HNO4_NASA94	M
Hydrogen Peroxide Photolysis for JPROC	%M3DATA%\nostudies\phot\H2O2_RADM88	M
Hydrogen Peroxide Photolysis for JPROC	%M3DATA%\nostudies\phot\H2O2_NASA94	M
Formaldehyde Photolysis to Radicals for JPROC	%M3DATA%\nostudies\phot\ HCHOrad_RADM88	M
Formaldehyde Photolysis to Radicals for JPROC	%M3DATA%\nostudies\phot\HCHOrad_CBIV 88	M
Formaldehyde Photolysis to Radicals for JPROC	%M3DATA%\nostudies\phot\ HCHOrad_NASA94	M
Formaldehyde Photolysis to Molecular Hydrogen for JPROC	%M3DATA%\nostudies\phot\ HCHOmol_RADM88	M
Formaldehyde Photolysis to Molecular Hydrogen for JPROC	%M3DATA%\nostudies\phot\ HCHOmol_CBIV88	M
Formaldehyde Photolysis to Molecular Hydrogen for JPROC	%M3DATA%\nostudies\phot\ HCHOmol_NASA94	M
Acetaldehyde Photolysis for JPROC	%M3DATA%\nostudies\phot\ALD_RADM88	M

TABLE	CC-1. Selected Datasets Under Nostudies	
Dataset Name	File Location	Tape
Acetaldehyde Photolysis for JPROC	%M3DATA%\nostudies\phot\ALD_CBIV88	M
Acetone Photolysis for JPROC	%M3DATA%\nostudies\phot\ ACETONE_RADM88	M
Methyl Ethyl Ketone Photolysis for JPROC	%M3DATA%\nostudies\phot\ KETONE_RADM88	M
Glyoxal Photolysis to Formaldehyde for JPROC	%M3DATA%\nostudies\phot\ GLYform_RADM88	M
Methyl Glyoxal Photolysis for JPROC	%M3DATA%\nostudies\phot\MGLY_RADM8 8	M
Unsaturated Dicarbonyl Photolysis for JPROC	%M3DATA%\nostudies\phot\UDC_RADM88	M
Methyl Hydrogen Peroxide Photolysis for JPROC	%M3DATA%\nostudies\phot\MHP_RADM88	M
Methyl Hydrogen Peroxide Photolysis for JPROC	%M3DATA%\nostudies\phot\MHP_NASA94	M
Organic Nitrate Photolysis for JPROC	%M3DATA%\nostudies\phot\ ORGNIT_RADM88	М
Glyoxal Photolysis to Molecular Hydrogen for JPROC	%M3DATA%\nostudies\phot\GLYmol_RADM88	M
Acrolein Photolysis for JPROC	%M3DATA%\nostudies\phot\ACROLEIN	M
Cray IEEE MM5 output files used as input to MCIP in the tutorial	%M3DATA%\nostudies\mm5\MET_36\ MMOUT_DOMAIN2	M

APPENDIX D

Copyrights and Trademarks



ObjectStore Release 5.1 for SPARC Solaris 2.7/SunPro (SunOS 5.4)

Copyright Object Design, Inc. 1989, 1990, 1991, 1992, 1993, 1994, 1995, 1996,

Object Design Inc. claims copyright in this computer program as an unpublished work, versions of which were created on the date(s) indicated in the foregoing notice. Claim of copyright does not imply waiver of Object Design Inc.'s other rights in the work.

This tape or disk and the program recorded on it are the property of Object Design Inc. Use of the programs (including examination, reproduction, modification, translation and disclosure) and transfer of the programs and the right to use the programs are all prohibited except by the express written authorization of Object Design, Inc.

"RESTRICTED RIGHTS LEGEND -- Use, duplication, or disclosure by the Government is subject to restrictions as set forth in subparagraph (c) (1) (ii) of the Rights in Technical Data and Computer Software clause at 252.227-7013 (48 CFR, Ch. 2). Contractor/manufacturer is Object Design, Inc., 25 Burlington Mall Road, Burlington, MA 01803."



License, Trademark, and Copyright Information

License Information

You have access to the Galaxy Application Environment (TM) software and documentation pursuant to the terms of a Software License Agreement granted by Ambiencia Information Systems, Inc.. As a user of this software and documentation, you are bound by the terms of the Software License Agreement. All rights, title, and interest to this software remain with Ambiencia Information Systems, Inc.

Use, reproduction, and disclosure of the software and documentation by the U.S. Government is subject to restrictions set forth in (i) FAR 52.227-14, (ii) FAR 52.227-19, (iii) DFAR 252.227-7013, or (iv) the Software License Agreement, as applicable, for limited rights technical data and restricted rights computer software. For purposes of the FAR, the software shall be deemed "unpublished" and licensed with disclosure prohibitions.

Contractor/subcontractor: Ambiencia Information Systems, Inc.

Trademark Acknowledgments

Galaxy Application Environment is a registered trademark and Vibe is a trademark of Ambiencia Information Systems, Inc. The Graphics Interchange Format is a copyright property and GIF is a service mark of CompuServe Incorporated. Helvetica is a registered trademark of Linotype Corporation. Microsoft is a registered trademark and Microsoft Windows, Windows NT, and ActiveX are trademarks of Microsoft Corporation. IRIX and Silicon Graphics are trademarks of Silicon Graphics, Inc. Motif and Open Software Foundation are trademarks of the Open Software Foundation, Inc. OPEN LOOK is a registered trademark of Novell, Inc. OS/2, AIX, and IBM are registered trademarks of International Business Machines Corporation. PostScript and Display Postscript are registered trademarks of Adobe Systems Incorporated. The PBM, PGM, PPM, and XBM image formats are owned and used by permission of Massachusetts Institute of Technology. X Window System is a trademark of X Consortium Inc. Sun, Java, Solaris, SunOS, and OpenWindows are trademarks or registered trademarks of Sun Microsystems, Inc. Unicode is a trademark of Unicode, Inc. UNIX and XWindow System are registered trademarks licensed exclusively by X/Open Company Ltd. Sybase is a registered trademark of Sybase, Inc.

Any other products or services mentioned or depicted in this document are identified by the trademarks or service marks of their respective companies or organizations.

Copyright

Copyright 1999-2001 Ambiencia Informations Systems, Inc., Rua Barao de Itapura, 2137, Cj. 75, Cep. 13076-000, Campinas - Sao Paulo - Brazil. All Rights Reserved. No portion of this document may be reproduced, transmitted, transcribed, stored in a retrieval system, or translated into any language, in any form or by any means, without the prior written consent of Ambiencia Information Systems, Inc.

The information contained herein is subject to change without notice. Therefore, Ambiencia Information Systems, Inc. assumes no responsibility for the accuracy of the information presented in this document beyond its current release date.

Orbix
OTOM

Orbix is a Registered Trademark of IONA Technologies Ltd.

While the information in this publication is believed to be accurate, IONA Technologies Ltd makes no warranty of any kind to this material including, but not limited to, the implied

warranties of merchantability and fitness for a particular purpose. IONA Technologies Ltd shall not be liable for errors contained herein, or for incidental or consequential damages in connection with the furnishing, performance or use of this material.

COPYRIGHT NOTICE

No part of this publication may be reproduced, stored in a retrieval system or transmitted, in any form or by any means, photocopying, recording or otherwise, without prior written consent of IONA Technologies Ltd. No third-party patent liability is assumed with respect to the use of the information contained herein. While very precaution has been taken in the preparation of this book, IONA Technologies Ltd assumes no responsibility for errors or omissions. This publication and features described herein are subject to change without notice.

Copyright (C) 1991-1995 IONA Technologies Ltd. All rights reserved.

The programs and information contained herein are licensed only pursuant to a license agreement that contains use, reverse engineering, disclosure and other restrictions; accordingly, it is "Unpublished - all rights reserved under the applicable copyright laws".

UNIX is a trademark of UNIX System Laboratories, Inc.

Windows, Windows 3.1, Windows NT and OLE Automation are trademarks of Microsoft Corp.

Isis is a trademark of Isis Distributed Systems, Inc.

ObjectStore is a trademark of Object Design, Inc.

ORB, Object Request Broker, OMG IDL, CORBA are trademarks of Object Management Group, Inc.

Solaris is a trademark of Sun Microsystems, Inc.

OSF is a trademark of the Open Software Foundation, Inc.

All other products of services mentioned in this manual are covered by the trademarks, service marks, or product names as designated by the companies who market those products.

Natagona
Netscape

BY CLICKING THE ACCEPTANCE BUTTON OR INSTALLING THE SOFTWARE, YOU ARE CONSENTING TO BE BOUND BY AND ARE BECOMING A PARTY TO THIS AGREEMENT. IF YOU DO NOT AGREE TO ALL OF THE TERMS OF THIS AGREEMENT, CLICK THE BUTTON THAT INDICATES YOU DO NOT ACCEPT THE TERMS AND DO NOT INSTALL THE SOFTWARE. (IF APPLICABLE, YOU MAY RETURN THE PRODUCT TO THE PLACE OF PURCHASE FOR A FULL REFUND.) IF THE COPY OF THE SOFTWARE YOU RECEIVED WAS ACCOMPANIED BY A PRINTED OR OTHER FORM OF "HARD-COPY" END USER LICENSE AGREEMENT

WHOSE TERMS VARY FROM THIS AGREEMENT, THEN THE HARD-COPY END USER LICENSE AGREEMENT GOVERNS YOUR USE OF THE SOFTWARE.

NETSCAPE CLIENT SOFTWARE END USER LICENSE AGREEMENT REDISTRIBUTION OR RENTAL NOT PERMITTED.

This Agreement sets forth the terms and conditions of your use of the accompanying Netscape client software product(s) (the "Software"). Any third party software that is provided with the Software with such third party's license agreement (in either electronic or printed form) is included for use at your option. If you choose to use such software, then such use shall be governed by such third party's license and not by this Agreement.

This Agreement has 3 parts. Part I applies if you have a free of charge license to the Software. Part II applies if you have purchased a license to the Software. Part III applies to all license grants. If you initially acquired a copy of the Software free of charge and you wish to purchase a license, contact Netscape Communications Corporation ("Netscape") on the Internet at http://home.netscape.com. As used in this Agreement, for residents of Europe, the Middle East and Africa, "Netscape" shall refer to Netscape Communications Ireland Limited; for residents of Japan, "Netscape" shall refer to Netscape Communications (Japan), Ltd.; for residents of all other countries, "Netscape" shall refer to Netscape Communications Corporation. For purposes of this Agreement, "Licensor" shall be defined as follows: If you have acquired a third party product or service and such product or service included the Software, then such third party shall be the Licensor. Otherwise, Netscape shall be the Licensor.

PART I - TERMS APPLICABLE WHEN LICENSE FEES NOT (YET) PAID (LIMITED TO EVALUATION, EDUCATIONAL AND NON-PROFIT USE).

LICENSE GRANT. Licensor grants you a non-exclusive license to use the Software free of charge if (a) you are a student, faculty member or staff member of an educational institution (K-12, junior college, college or university, or the international equivalent, or a library), a staff member of a religious organization or an employee of an organization which meets Licensor's criteria for a charitable non-profit organization; or (b) your use of the Software is for the purpose of evaluating whether to purchase an ongoing license to the Software. The evaluation period for use by or on behalf of a commercial entity is limited to ninety (90) days; evaluation use by others is not subject to this ninety (90) day limit. Government agencies (other than public libraries) are not considered educational, religious or charitable non-profit organizations for purposes of this Agreement. If you are using the Software free of charge, you are not entitled to hard-copy documentation, support or telephone assistance. If you fit within the description above, you may use the Software in the manner described in Part III below under "Scope of Grant."

DISCLAIMER OF WARRANTY. Free of charge Software is provided on an "AS IS" basis, without warranty of any kind, including without limitation the warranties that the Software is

free of defects, merchantable, fit for a particular purpose or non-infringing. The entire risk as to the quality and performance of the Software is borne by you. Should the Software prove defective in any respect, you and not Licensor or its suppliers assume the entire cost of any service and repair. In addition, the security mechanisms implemented by the Software have inherent limitations, and you must determine that the Software sufficiently meets your requirements. This disclaimer of warranty constitutes an essential part of this Agreement. No use of the Software without payment of license fees to Licensor is authorized hereunder except under this Disclaimer.

PART II - TERMS APPLICABLE WHEN LICENSE FEES PAID

LICENSE GRANT. Subject to payment of applicable license fees, Licensor grants to you a non-exclusive license to use the Software and accompanying documentation ("Documentation") in the manner described in Part III below under "Scope of Grant."

LIMITED WARRANTY. Licensor warrants that for a period of ninety (90) days from the date of acquisition, the Software, if operated as directed, will substantially achieve the functionality described in the Documentation. Licensor does not warrant, however, that your use of the Software will be uninterrupted or that the operation of the Software will be error-free or secure. In addition, the security mechanisms implemented by the Software have inherent limitations, and you must determine that the Software sufficiently meets your requirements. Licensor also warrants that the media containing the Software, if provided by Licensor, is free from defects in material and workmanship and will so remain for ninety (90) days from the date you acquired the Software. Licensor's sole liability for any breach of this warranty shall be, in Licensor's sole discretion: (i) to replace your defective media or Software; or (ii) to advise you how to achieve substantially the same functionality with the Software as described in the Documentation through a procedure different from that set forth in the Documentation; or (iii) if the above remedies are impracticable, to refund the license fee you paid for the Software. Repaired, corrected, or replaced Software and Documentation shall be covered by this limited warranty for the period remaining under the warranty that covered the original Software, or if longer, for thirty (30) days after the date (a) of delivery to you of the repaired or replaced Software, or (b) Licensor advised you how to operate the Software so as to achieve substantially the same functionality described in the Documentation.

Only if you inform Licensor of your problem with the Software during the applicable warranty period and provide evidence of the date you purchased a license to the Software will Licensor be obligated to honor this warranty. Licensor will use reasonable commercial efforts to repair, replace, advise or, for individual consumers, refund pursuant to the foregoing warranty within thirty (30) days of being so notified.

If any modifications are made to the Software by you during the warranty period; if the media is subjected to accident, abuse, or improper use; or if you violate the terms of this Agreement, then this warranty shall immediately terminate. Moreover, this warranty shall not apply if the

Software is used on or in conjunction with hardware or software other than the unmodified version of hardware and software with which the Software was designed to be used as described in the Documentation.

THIS IS A LIMITED WARRANTY, AND IT IS THE ONLY WARRANTY MADE BY LICENSOR OR ITS SUPPLIERS. LICENSOR MAKES NO OTHER WARRANTIES, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, AND NONINFRINGEMENT OF THIRD PARTIES' RIGHTS. YOU MAY HAVE OTHER STATUTORY RIGHTS. HOWEVER, TO THE FULL EXTENT PERMITTED BY LAW, THE DURATION OF STATUTORILY REQUIRED WARRANTIES, IF ANY, SHALL BE LIMITED TO THE ABOVE LIMITED WARRANTY PERIOD. MOREOVER, IN NO EVENT WILL WARRANTIES PROVIDED BY LAW, IF ANY, APPLY UNLESS THEY ARE REQUIRED TO APPLY BY STATUTE NOTWITHSTANDING THEIR EXCLUSION BY CONTRACT. NO DEALER, AGENT, OR EMPLOYEE OF LICENSOR IS AUTHORIZED TO MAKE ANY MODIFICATIONS, EXTENSIONS, OR ADDITIONS TO THIS LIMITED WARRANTY.

PART III - TERMS APPLICABLE TO ALL LICENSE GRANTS

SCOPE OF LICENSE GRANT.

You may:

- * use the Software on any single computer;
- * use the Software on a second computer so long as only one (1) copy is used at a time;
- * use the Software on a network, provided that a licensed copy of the Software has been acquired for each person permitted to access the Software through the network;
- * make a single copy the Software for archival purposes, provided the copy contains all of the original Software's proprietary notices; or
- * if you have purchased a license for multiple copies of the Software, make the total number of copies of Software (but not the Documentation) stated on the packing slip(s), invoice(s), or Certificate(s) of Authenticity, provided any copy must contain all of the original Software's proprietary notices. The number of copies on the packing slip(s), invoice(s), or Certificate(s) of Authenticity is the total number of copies that may be made for all platforms. Additional copies of Documentation may be purchased from Licensor.

You may not:

- * permit other individuals to use the Software except under the terms listed above;
- * permit concurrent use of the Software;
- * modify, translate, reverse engineer, decompile, disassemble (except and solely to the extent an applicable statute expressly and specifically prohibits such restrictions), or create derivative works based on the Software;
- * copy the Software other than as specified above;
- * rent, lease, grant a security interest in, or otherwise transfer rights to the Software; or
- * remove any proprietary notices or labels on the Software.

ENCRYPTION. If the Software contains cryptographic features, then you may wish to obtain a signed digital certificate from a certificate authority or a certificate server in order to utilize certain of the cryptographic features. You may be charged additional fees for certification services. You are responsible for maintaining the security of the environment in which the Software is used and the integrity of the private key file used with the Software. In addition, the use of digital certificates is subject to the terms specified by the certificate provider, and there are inherent limitations in the capabilities of digital certificates. If you are sending or receiving digital certificates, you are responsible for familiarizing yourself with and evaluating such terms and limitations. If the Software is a Netscape product with Fortezza, you will also need to obtain PC Card Readers and Fortezza Crypto Cards to enable the Fortezza features.

TITLE. Title, ownership rights, and intellectual property rights in the Software shall remain in Netscape and/or its suppliers. The Software is protected by copyright and other intellectual property laws and by international treaties. Title and related rights in the content accessed through the Software is the property of the applicable content owner and is protected by applicable law. The license granted under this Agreement gives you no rights to such content.

TERMINATION. This Agreement and the license granted hereunder will terminate automatically if you fail to comply with the limitations described herein. Upon termination, you must destroy all copies of the Software and Documentation.

EXPORT CONTROLS. None of the Software or underlying information or technology may be downloaded or otherwise exported or re-exported (i) into (or to a national or resident of) Cuba, Iraq, Libya, Sudan, North Korea, Iran, Syria or any other country to which the U.S. has embargoed goods; or (ii) to anyone on the U.S. Treasury Department's list of Specially Designated Nationals or the U.S. Commerce Department's Table of Denial Orders. By downloading or using the Software, you are agreeing to the foregoing and you are representing and warranting that you are not located in, under the control of, or a national or resident of any such country or on any such list. In addition, you are responsible for complying with any local

laws in your jurisdiction which may impact your right to import, export or use the Software.

If the Software is identified as a not-for-export product (for example, on the box, media or in the installation process), then, unless you have an exemption from the United States Department of State, the following applies: EXCEPT FOR EXPORT TO CANADA FOR USE IN CANADA BY CANADIAN CITIZENS, THE SOFTWARE AND ANY UNDERLYING TECHNOLOGY MAY NOT BE EXPORTED OUTSIDE THE UNITED STATES OR TO ANY FOREIGN ENTITY OR "FOREIGN PERSON" AS DEFINED BY U.S. GOVERNMENT REGULATIONS, INCLUDING WITHOUT LIMITATION, ANYONE WHO IS NOT A CITIZEN, NATIONAL OR LAWFUL PERMANENT RESIDENT OF THE UNITED STATES. BY DOWNLOADING OR USING THE SOFTWARE, YOU ARE AGREEING TO THE FOREGOING AND YOU ARE WARRANTING THAT YOU ARE NOT A "FOREIGN PERSON" OR UNDER THE CONTROL OF A "FOREIGN PERSON."

LIMITATION OF LIABILITY. UNDER NO CIRCUMSTANCES AND UNDER NO LEGAL THEORY, TORT, CONTRACT, OR OTHERWISE, SHALL LICENSOR OR ITS SUPPLIERS OR RESELLERS BE LIABLE TO YOU OR ANY OTHER PERSON FOR ANY INDIRECT, SPECIAL, INCIDENTAL, OR CONSEQUENTIAL DAMAGES OF ANY CHARACTER INCLUDING, WITHOUT LIMITATION, DAMAGES FOR LOSS OF GOODWILL, WORK STOPPAGE, COMPUTER FAILURE OR MALFUNCTION, OR ANY AND ALL OTHER COMMERCIAL DAMAGES OR LOSSES. IN NO EVENT WILL LICENSOR BE LIABLE FOR ANY DAMAGES IN EXCESS OF THE AMOUNT LICENSOR RECEIVED FROM YOU FOR A LICENSE TO THE SOFTWARE, EVEN IF LICENSOR SHALL HAVE BEEN INFORMED OF THE POSSIBILITY OF SUCH DAMAGES, OR FOR ANY CLAIM BY ANY THIRD PARTY. THIS LIMITATION OF LIABILITY SHALL NOT APPLY TO LIABILITY FOR DEATH OR PERSONAL INJURY RESULTING FROM LICENSOR'S NEGLIGENCE TO THE EXTENT APPLICABLE LAW PROHIBITS SUCH LIMITATION. SOME JURISDICTIONS DO NOT ALLOW THE EXCLUSION OR LIMITATION OF INCIDENTAL OR CONSEQUENTIAL DAMAGES, SO THIS EXCLUSION AND LIMITATION MAY NOT APPLY TO YOU.

HIGH RISK ACTIVITIES. The Software is not fault-tolerant and is not designed, manufactured or intended for use or resale as on-line control equipment in hazardous environments requiring fail-safe performance, such as in the operation of nuclear facilities, aircraft navigation or communication systems, air traffic control, direct life support machines, or weapons systems, in which the failure of the Software could lead directly to death, personal injury, or severe physical or environmental damage ("High Risk Activities"). Accordingly, Licensor and its suppliers specifically disclaim any express or implied warranty of fitness for High Risk Activities.

MISCELLANEOUS. This Agreement represents the complete agreement concerning the license granted hereunder and may be amended only by a writing executed by both parties. THE ACCEPTANCE OF ANY PURCHASE ORDER PLACED BY YOU IS EXPRESSLY MADE

CONDITIONAL ON YOUR ASSENT TO THE TERMS SET FORTH HEREIN, AND NOT THOSE IN YOUR PURCHASE ORDER. If any provision of this Agreement is held to be unenforceable, such provision shall be reformed only to the extent necessary to make it enforceable. This Agreement shall be governed by California law, excluding conflict of law provisions (except to the extent applicable law, if any, provides otherwise). The application of the United Nations Convention on Contracts for the International Sale of Goods is expressly excluded.

U.S. GOVERNMENT END USERS. The Software is a "commercial item," as that term is defined in 48 C.F.R. 2.101 (Oct. 1995), consisting of "commercial computer software" and "commercial computer software documentation," as such terms are used in 48 C.F.R. 12.212 (Sept. 1995). Consistent with 48 C.F.R. 12.212 and 48 C.F.R. 227.7202-1 through 227.7202-4 (June 1995), all U.S. Government End Users acquire the Software with only those rights set forth herein.

Netscape Client Software EULA	Rev. 072197	
	ARC/INFO	

Copyright (C) 1982-2000 Environmental Systems Research Institute, Inc. All rights reserved.

RESTRICTED/LIMITED RIGHTS LEGEND

U.S. Government Restricted/Limited Rights: Any software, documentation, and/or data delivered hereunder is subject to the terms of the License Agreement. In no event shall the Government acquire greater than RESTRICTED/LIMITED RIGHTS. At a minimum, use, duplication or disclosure by the Government is subject to restrictions as set forth in FAR 12.211/12.212 [Commercial Technical Data/Computer Software]; DFARS 252.227-7015 (NOV 1995) [Technical Data]; and/or DFARS 227.7202 [Computer Software], as applicable. Contractor/Manufacturer is Environmental Systems Research Institute, Inc., 380 New York Street, Redlands, CA 92373-8100 USA.

ESRI, ARC/INFO, WorkStation ARC/INFO, and ArcView are registered trademarks and ArcStorm, ArcScan, ArcPress, ArcDocs, ArcTools, AML, ARCEDIT, ARCPLOT, Spatial Data base Engine, (SDE), the ESRI corporate logo, and the ArcView logo are trademarks of Environmental Systems Research Institute, Inc.

Copyright (C) 1982-2000 Environmental Systems Research Institute, Inc. All rights reserved.

ARC Version 8.0

This software is provided with RESTRICTED AND LIMITED RIGHTS. Use, duplication, or disclosure by the Government is subject to the restrictions as set forth in FAR 52.227-14 (JUN 1987) Alternate III (g)(3) (JUN 1987), FAR 52.227-19 (JUN 1987), or DFARS 552.227-7013 (c)(1)(ii) (OCT 1988), as applicable. Contractor/Manufacturer is Environmental Systems Research Institute, Inc. (ESRI) 380 New York St. Redlands, CA 92373.

0 4 0
SAS

Copyright (C) 1989-2000 by SAS Institute Inc., Cary, NC, USA. Unpublished - All Rights Reserved.

RESTRICTED RIGHTS LEGEND

Use, duplication or disclosure by the U.S. Government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software Clause at DFARS 252.227-7013.

SAS Institute Inc., SAS Campus Drive, Cary, North Carolina, USA 27513.



First Printing, June 1994 Revised, April 1995 Revised, April 1997

Digital Equipment Corporation makes no representations that the use of its products in the manner described in this publication [i.e., Digital Fortran Compiler for Windows] will not infringe on existing or future patent rights, nor do the descriptions contained in this publication imply the granting of licenses to make, use, or sell equipment or software in accordance with the description.

Possession, use, or copying of the software described in this publication is authorized only pursuant to a valid written license from Digital or an authorized sub licensor.

(C)Digital Equipment Corporation 1997. All Rights Reserved.

Cover graphic, photographs: Copyright(C) 1997 PhotoDisc, Inc.

Cover graphic, image: CERN, European Laboratory for Particle Physics: ALICE detector on

CERN's future accelerator, the LHC, Large Hadron Collinder.

The following are trademarks of Digital Equipment Corporation: Alpha AXP, AlphaGeneration, AXP, DEC, DEC Fortran, Digital, OpenVMS, VAX, VMS, and the DIGITAL logo.

The following are third-party trademarks:

CRAY is a registered trademark of Cray Research, Inc.

IBM is a registered trademark of International Business Machines, Inc.

IEEE is a registered trademark of the Institute of Electrical and Electronics Engineers, Inc. Intel and Pentium are registered trademarks of Intel Corporation.

Microsoft, MS, MS-DOS, Windows, and Windows 95 are registered trademarks, and NT and WindowsNT are trademarks of Microsoft Corporation.

OSF and OSF/1 are registered trademarks of the Open Software Foundation, Inc.

UNIX is a registered trademark in the United States and other countries licensed exclusively through X/Open Company Ltd.

All other trademarks and registered trademarks are the property of their respective holders.



Copyright ©1990 Cray Research, Inc. All Rights Reserved. This manual or parts thereof may not be reproduced in any form unless permitted by contract or by written permission of Cray Research, Inc.

CRAY®, CRAY-1®, Cray Ada®, CRAY Y-MP®, HSX®, SSD®, UNICOS® and X-MP EA® are federally registered trademarks and AutotaskingTM, CF77TM, CFTTM, CFT2TM, CFT77TM, COLTM, CRAY X-MPTM, CRAY Y-MP2ETM, CRAY-2TM, CSIMTM, Delivering the power...TM, IOSTM, OLNETTM, RQSTM, SEGLDRTM, and SUPERLINKTM are trademarks of Cray Research Inc.

UNIX is a trademark of AT&T. VMEbus is a trademark of Motorola, Inc.

The UNICOS operating system is derived from the AT&T UNIX Operating System V operating system. UNICOS is also based in part on the Fourth Berkeley Software Distribution under license from The Regents of the University of California.

Operating System - CRAY UNICOS


Copyright ©1986, 1987, 1988 Cray Research, Inc. This manual or parts thereof may not be reproduced unless permitted by contract or by written permission of Cray Research, Inc.

CRAY, CRAY-1, SSD, and UNICOS are registered trademarks and CFT, CFT77, CFT2, COS, CRAY-2, CRAY X-MP, CRAY X-MP EA, CRAY Y-MP, CSIM, HSX, IOS, SEGLDR, and SUPERLINK are trademarks of Cray Research, Inc.

3B20 is a trademark of AT&T. Apollo and DOMAIN are registered trademarks of Apollo Computer Inc. CDC is a registered trademark of Control Data Corporation. DEC, VAX, and VMS are trademarks of Digital Equipment Corporation. IBM is a registered trademark of International Business Machines Corporation. IRIS is a trademark of Silicon Graphics, Inc. Pyramid is a trademark of Pyramid Technology corporation. Sun Microsystems is a trademark of Sun Microsystems, Inc. UNIX is a trademark of AT&T.

The TCP-IP documentation is copyrighted by the Wollongong Group and may not be reproduced, transmitted, transcribed, stored in a retrieval system, or translated into any language or computer language, in any form or by any means, electronic, mechanical, magnetic, optical, chemical, manual or otherwise, except as provided in the license agreement governing the documentation or by written permission of The Wollongong Group, Inc., 1129 San Antonio Road, Palo Alto, California, 943403. The Wollongong software and documentation is based in part on the Fourth Berkeley Software Distribution under license from The Regents of the University of California. ©The Wollongong Group, Inc., 1985.

The UNICOS operating system is derived from the AT&T UNIX Operating System V operating system. UNICOS is also based in part on the Fourth Berkeley Software Distribution under license from The Regents of the University of California.



©Copyright 1990, Silicon Graphics, Inc. - All rights reserved.

This document contains proprietary information of Silicon Graphics, Inc. The contents of this document may not be disclosed to third parties, copied or duplicated in any form, in whole or in part, without the express written permission of Silicon Graphics, Inc.

Restricted Rights Legend

Use, duplication or disclosure of the technical data contained in this document by the Government is subject to restrictions as set forth in subdivision (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 52.227-7013, and/or in similar or successor clauses in the FAR, or the DOD or NASA FAR Supplement. Unpublished rights reserved under the Copyright Laws of the United States. Contractor/manufacturer is Silicon Graphics, inc., 2011 N. Shoreline Blvd., Mountain View, CA 94039-7311.

Silicon Graphics and IRIS are registered trademarks and IRIX, Personal IRIS, and Efast are trademarks of Silicon Graphics, Inc. Ethernet is a registered trademark of the Xerox Corporation. Motif is a trademark of Open Software foundation. NFS is a trademark of Sun Microsystems, Inc. UNIX is a registered trademark of UNIX System Laboratories.

Microsoft Internet Explorer (see http://www.microsoft/com/ie)

NOTICE SPECIFIC TO SOFTWARE AVAILABLE ON THIS WEBSITE

Any software that is made available to download from this server ("Software") is the copyrighted work of Microsoft and/or its suppliers. Use of the Software is governed by the terms of the end user licence agreement, if any, which accompanies or is included with the Software ("Licence Agreement"). An end user will be unable to install any Software that is accompanied by or includes a Licence Agreement, unless he or she first agrees to the Licence Agreement terms.

The Software is made available for downloading solely for use by end users according to the Licence Agreement. Any reproduction or redistribution of the Software not in accordance with the Licence Agreement is expressly prohibited by law, and may result in severe civil and criminal penalties. Violators will prosecuted to the maximum extent possible.

WITHOUT LIMITING THE FOREGOING, COPYING OR REPRODUCTION OF THE SOFTWARE TO ANY OTHER SERVER OR LOCATION FOR FURTHER REPRODUCTION OR REDISTRIBUTION IS EXPRESSLY PROHIBITED.

THE SOFTWARE IS WARRANTED, IF AT ALL, ONLY ACCORDING TO THE TERMS OF THE LICENCE AGREEMENT. EXCEPT AS WARRANTED IN THE LICENCE AGREEMENT, MICROSOFT CORPORATION HEREBY DISCLAIMS ALL WARRANTIES AND CONDITIONS WITH REGARD TO THE SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES AND CONDITIONS OF MERCHANTIBILITY, FITNESS FOR A PARTICULAR PURPOSE, TITLE AND NON-INFRINGEMENT.

RESTRICTED RIGHTS LEGEND. Any Software which is downloaded from this Server for or on behalf of the United States of America, its agencies and/or instrumentalities ("U.S. Government"), is provided with Restricted Rights. Use, duplication, or disclosure by the U.S. Government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.227-7013 or subparagraphs (c)(1) and (2) of the Commercial Computer Software - Restricted Rights at 48 CFR 52.227-19, as applicable. Manufacturer is Microsoft Corporation, One Microsoft Way, Redmond, WA 98052-6399.

NOTICE SPECIFIC TO DOCUMENTS AVAILABLE ON THIS WEBSITE

Permission to use Documents (such as white papers, press releases, data sheets and FAQs) from this server ("Server") is granted, provided that (1) the below copyright notice appears in all copies and that both the copyright notice and this permission notice appear, (2) use of such Documents from this Server is for informational and non-commercial or personal use only and will not be copied or posted on any network computer or broadcast in any media, and (3) no modifications or any Documents are made. Use for any other purpose is expressly prohibited by law, and may result in severe civil and criminal penalties. Violators will be prosecuted to the maximum extent possible.

Documents specified above do not include the design or layout of the microsoft.com web site or any other Microsoft owned, operated, licensed or controlled site. Elements of Microsoft web sites are protected by trade dress and other laws and may not be copied or imitated in whole or in part. No logo, graphic, sound or image from any Microsoft web site may be copied or retransmitted unless expressly permitted by Microsoft.

MICROSOFT AND/OR ITS RESPECTIVE SUPPLIERS MAKE NO REPRESENTATIONS ABOUT THE SUITABILITY OF THE INFORMATION CONTAINED IN THE DOCUMENTS AND RELATED GRAPHICS PUBLISHED ON THIS SERVER FOR ANY PURPOSE. ALL SUCH DOCUMENTS AND RELATED GRAPHICS ARE PROVIDED "AS IS" WITHOUT WARRANTY OF ANY KIND. MICROSOFT AND/OR ITS RESPECTIVE SUPPLIERS HEREBY DISCLAIM ALL WARRANTIES AND CONDITIONS WITH REGARD TO THIS INFORMATION, INCLUDING ALL IMPLIED WARRANTIES AND CONDITIONS OF MERCHANTIBILITY, FITNESS FOR A PARTICULAR PURPOSE, TITLE AND NON-INFRINGEMENT. IN NO EVENT SHALL MICROSOFT AND/OR ITS RESPECTIVE SUPPLIERS BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF INFORMATION AVAILABLE FROM THIS SERVER.

THE DOCUMENTS AND RELATED GRAPHICS PUBLISHED ON THIS SERVER COULD INCLUDE TECHNICAL INACCURACIES OR TYPOGRAPHICAL ERRORS. CHANGES ARE PERIODICALLY ADDED TO THE INFORMATION HEREIN. MICROSOFT AND/OR ITS RESPECTIVE SUPPLIERS MAY MAKE IMPROVEMENTS AND/OR CHANGES IN THE PRODUCT(S) AND/OR THE PROGRAM(S) DESCRIBED HEREIN AT ANY TIME. NOTICES REGARDING SOFTWARE, DOCUMENTS AND SERVICES AVAILABLE ON THIS WEBSITE.

IN NO EVENT SHALL MICROSOFT AND/OR ITS RESPECTIVE SUPPLIERS BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR

PERFORMANCE OF SOFTWARE, DOCUMENTS, PROVISION OF OR FAILURE TO PROVIDE SERVICES, OR INFORMATION AVAILABLE FROM THIS SERVER. LINKS TO THIRD PARTY SITES THE LINKS IN THIS AREA WILL LET YOU LEAVE MICROSOFT'S SITE. THE LINKED SITES ARE NOT UNDER THE CONTROL OF MICROSOFT AND MICROSOFT IS NOT RESPONSIBLE FOR THE CONTENTS OF ANY LINKED SITE OR ANY LINK CONTAINED IN A LINKED SITE, OR ANY CHANGES OR UPDATES TO SUCH SITES. MICROSOFT IS PROVIDING THESE LINKS TO YOU ONLY AS A CONVENIENCE, AND THE INCLUSION OF ANY LINK DOES NOT IMPLY ENDORSEMENT BY MICROSOFT OF THE SITE.

COPYRIGHT NOTICE. Copyright © 1998 Microsoft and/or its suppliers, One Microsoft Way, Redmond, Washington 98052-6399 U.S.A. All right reserved.

TRADEMARKS. Microsoft, Windows, Windows NT, MSN, The Microsoft Network and/or other Microsoft products referenced herein are either trademarks or registered trademarks of Microsoft. Other product and company names mentioned herein may be the trademarks of their respective owners.

The names of companies, products, people, characters and/or data mentioned herein are fictitious and are in no way intended to represent any real individual, company, product or event, unless otherwise noted.

Any rights not expressly granted herein are reserved.

0 1000 14:

Contact www@microsoft.com or webmaster@msn.com with questions or problems, as appropriate.

© 1998 Microsoft Corporation. All rights reserved. Terms of Use. Last updated: February 24 1998
WFTPD
WFTPD (by Texas Imperial Software) 32-bit version 2.40 8/11/1998
Copyright (c) 1995-98 Texas Imperial Software Winsock FTP Daemon for MS Windows 3.1, 95 & NT
Operating System - Windows NT

Microsoft, MS-DOS, Windows, Windows NT, ActiveX, BackOffice, and MSN are either

registered trademarks or trademarks of Microsoft Corporation in the United States and/or other countries.

Microsoft may have patents or pending patent applications, trademarks, copyrights, or other intellectual property rights covering subject matter in this document. The furnishing of this document does not give you any license to these patents, trademarks, copyrights, or other intellectual property rights expressly provide in any written license agreement from Microsoft.

APPENDIX E

CMAQ Model Change Notes

CMAQ Model Change Notes

1. SO2 reactions in CB4 Mechanisms

The CB4 chemical mechanisms originally incorporated in Models-3/CMAQ were based on a version of CB4 used in the UAM-V [Systems Guide to the Urban Airshed Model (UAM-V), Systems Applications International, October, 1993]. That version included a first-order decay reaction of SO2 for simulating sulfate formation via aqueous processes when the latter are not modeled explicitly. As a result, this reaction should not be included in CMAQ versions of the mechanism when CMAQ simulations explicitly include clouds. With this update, all CB4 mechanism configurations in the CMAQ system have been modified such that the rate constant for the reaction <83> (SO2 = SULF) is zero. In addition, the rate constant for reaction <82> (SO2 + OH = SULF + HO2) has been changed from the original UAM-V Arrhenius form to the same Troe form used in the Models-3/CMAQ RADM2 mechanisms and recommended by NASA-JPL (Chemical Kinetics and Photochemical data for Use in Stratospheric Modeling, Evaluation Number 12, National Aeronautics and Space Administration, Jet Propulsion laboratory, California Institute of Technology, January, 1997).

2. Chemical Mechanism Processor Update

The Chemical Mechanism Processor (MP) in Models-3/CMAQ reads a chemical mechanism reactions file (mech.def) and generates two FORTRAN include files (RXDT.EXT and RXCM.EXT) that contain the mechanistic data that are used in CMAQ simulations. Part of those data include rate constant parameters that are sometimes too small to be represented by 32-bit single-precision numbers. As a result, variables holding rate constant parameters were typed REAL*8 to circumvent this problem. In previous releases, these variables were initialized with DATA statements that used E-format. On some compilers (particularly f90 compilers), this procedure will result in some of the small rate constant parameters being initialized to zero rather than their small value. Although effects could vary from compiler-to-compiler, the most probable consequence of this problem is to cause the RADM2 rate constant for the reaction HO2 + HO2 + H2O2 = H2O2 to be too low. To correct this problem, the MP program has been modified to generate rate constant data in D-format for all REAL*8 variables, and all mechanism include files in the archive have been re-generated with the D-format.

3. Aerosol Floating Point Exception Problem

The previous release of the AERO2 module can sometimes result in a floating point exception when the ammonium to sulfate ratio becomes very low. The AERO2 module has been modified to avoid this problem under these conditions.

APPENDIX F

Models-3 Version 4.1 Release Notes and SMOKE Information

RELEASE NOTES OF MODELS-3 (VERSION 4.1)

CONTRACT NO. 68-W-99-002 TASK ORDER NO. 010

Prepared for:

United States Environmental Protection Agency
Office of Research and Development
National Exposure Research Laboratory
Mail Drop 80
Research Triangle Park, NC 27711

Task Order Project Officer:

William G. Benjey

Prepared by:

Systems Development Center Science Applications International Corporation 6565 Arlington Boulevard Falls Church, VA 22042

CONTENTS

1.0	INTRODUCTION F-5					
	1.1	Purpos	se F-6			
	1.2	Scope	F-6			
	1.3	Identif	ication F-6			
2.0	REI	FEREN(CES F-6			
3.0	SUN	MMARY	OF FUNCTIONALITY F-7			
4.0	DE	GREE O	F FUNCTIONALITY PROVIDED			
	4.1		es Since Last Release F-9			
		4.1.1	Data Base F-9			
		4.1.2	Presenter			
		4.1.3	Study Planner			
		4.1.4	Science Manager			
		4.1.5	Model Builder			
		4.1.6	Tools Manager F-10			
		4.1.7	SMOKE, SMOKE Tool, MEPPS, MEPRO and IDA F-10			
	4.2	Assum	ptions, Limitations, and Problems F-11			
		4.2.1	Presenter			
		4.2.2	Dataset Manager F-13			
		4.2.3	Study Planner			
		4.2.4	Strategy Manager F-14			
		4.2.5	Program Manager F-14			
		4.2.6	Science Manager F-14			
		4.2.7	Model Builder			
		4.2.8	Tools Manager F-15			
		4.2.9	Execution Manager F-15			
		4.2.10	File Migrator F-15			
		4.2.11	Help F-16			
		4.2.12	File Convertor			
5.0	INS	STALLA	ATION INSTRUCTIONS			
API	PEND	IX F-1	SMOKE TOOL DOCUMENTATION			

EXHIBITS

Exhibit 1. Models-3 Framewo	k Components &	Integrated Programs		F-	8
-----------------------------	----------------	---------------------	--	----	---

1.0 INTRODUCTION

The U.S. Environmental Protection Agency (EPA) is empowered by current legislation to address today's important, grand challenge environmental problems, such as air quality management and linked air and water quality management. The use of environmental models is essential to EPA's cost effective accomplishment of its mission. As part of its High Performance Computing and Communications (HPCC) program, the Agency has initiated the development of a third-generation air quality modeling system called Models-3. Models-3 directly supports the HPCC program goal of using emerging computing and communications technology to:

- Develop the Agency's capability to perform complex multi-pollutant and cross-media pollutant studies that are currently not feasible due to computational limitations.
- Build federal, state, and industrial capabilities to use advanced assessment tools directly responsive to the needs for environmental management.
- Position the Agency to more easily integrate emerging computing and communications technology into environmental assessment tools, ensuring the most reliable and timely response to key environmental issues.

The Models-3 project is one of several being developed under the HPCC program. In many respects, however, Models-3 is the primary focus of EPA's HPCC research activities in that all the other projects under HPCC are, in one way or another, going to make significant contributions to enhance the capabilities of the Models-3 system. The other projects include: 1) linkage of air and water quality models, 2) development and performance evaluation of numerical algorithms on parallel architectures for key environmental processes, 3) development of training and technology transfer approaches to provide state, federal, and industrial air quality scientists and decision makers with credible and useful air quality modeling and decision support tools, 4) implementation of advanced computing hardware, software, and network infrastructure to support HPCC research activities, 5) development of advanced collaboratory visualization and analysis techniques, and 6) outreach activities designed to introduce more EPA researchers to the benefits of HPCC technology in their own areas of interest.

Legal Authority: The High Performance Computing Act of 1991 authorized EPA to perform research directed toward incorporating advances in computing and communications technology into EPA's environmental assessment applications and transferring these advanced tools to key state, federal, and industrial users with decision-making responsibility.

Regulatory Authority: As mandated by Congress in the 1990 Clean Air Act Amendments, the states are required to use photochemical grid models, such as the Urban Airshed Model (UAM) and the Regional Oxidant Model (ROM), to develop credible modeling demonstrations for attaining the National Ambient Air Quality Standards (NAAQS) as part of their State

Implementation Plans.

Regional Acid Deposition Model (RADM) applications are required to support EPA client and policy offices, EPA regional offices, and the states in implementing mandates of the 1990 Clean Air Act Amendments, special agreements between states, and treaty obligations under the U.S.—Canada Air Quality Agreement and the U.N. Economic Commission for Europe. The capabilities of RADM and ROM are improved and incorporated into the Community Multi-Scale Air Quality (CMAQ) model that is a part of the Models-3 Air Quality Modeling framework. CMAQ is a multi-pollutant model, enabling a unified "one-atmosphere" modeling approach and more realistic modeling of chemical interactions in meeting many of the air quality modeling needs of the 1990 Clean Air Act.

1.1 Purpose

This document provides new information not appearing in other Models-3 documentation and discusses changes since the last software release (Version 4.0). Anyone encountering a problem with Models-3 should check this document.

1.2 Scope

This document covers the Models-3 framework, the SMOKE Tool, and problems that may occur in getting to the individual models or tools used in the system. Problems with the actual models or tools are not covered in this document.

1.3 Identification

The sponsor of Models-3 is the National Exposure Research Laboratory (NERL) in EPA's Office of Research and Development. Work on Version 4.1 of Models-3 was performed under Mission Oriented Systems Engineering Support (MOSES) Task Order 002-010. The System Development Center (SDC) product control number for this release is SDC-0002-010-SR-3005.

2.0 REFERENCES

Byun, D.W. and J.K.S. Ching. *Science Algorithms of the EPA Models-3 Community Multiscale Air Quality (CMAQ) Modeling System.* EPA EPA/600/R-99/030, National Exposure Research Laboratory, Research Triangle Park, NC, 768 pp. (1999).

Novak, J.H., R.L. Dennis, D.W. Byun, J.E. Pleim, K.J. Galluppi, C.J. Coats, S. Chall, & M.A. Vouk. *EPA Third Generation Air Quality Modeling System, Models-3 Volume 1: Concept.* EPA/600/R95/084, National Exposure Research Laboratory, Research Triangle Park, NC, 55 pp. (1995).

System Installation and Operation Manual for the EPA Third-Generation Air Quality Modeling System (Models-3 Version 4.1 for Sun Unix and NT), National Exposure Laboratory Research Laboratory, Research Triangle Park, NC, (2001).

EPA Third Generation Air Quality Modeling System, Models-3 Volume 9b: User Manual. EPA/600/R-98/069(b), National Exposure Research Laboratory, Research Triangle Park, NC, 833 pp. (1998) (To Be Updated).

EPA Third Generation Air Quality Modeling System, Models-3 Volume 9c: User Manual: Standard Tutorial. EPA/600/R-98/069(c), National Exposure Research Laboratory, Research Triangle Park, NC, 387 pp. (1998) (To Be Updated).

Revised Project Plan for Implementation Support, Maintenance, and Enhancement of the Third Generation Air Quality Modeling System (Models-3), SDC-0002-010-SR-3001A, September 22, 2000.

3.0 SUMMARY OF FUNCTIONALITY

Models-3 is not a single model or modeling system, but rather a problem-solving environment comprising components that help you build, evaluate, and apply air quality models. Each shaded rectangle shown on Exhibit 1 represents a component that helps you perform major functions associated with environmental modeling.

Models-3's Object Oriented Data Base Management System (OO DBMS) provides a centralized method for managing and sharing data, metadata (information about data), program and/or script executables, and relationships and dependencies among executables and data needed for a specific modeling study. Each of the components communicates with the OO DBMS as shown in Exhibit 1. These components serve as user-friendly tools for accessing or modifying datasets and program source code, developing program or script executables, performing model simulations, and visualizing and analyzing model simulation results.




Exhibit 1. Models-3 Framework Components & Integrated Programs

The major Models-3 framework components are:

- **Science Manager** allows you to define globally shared information on key science components.
- **Dataset Manager** provides you with the capability to register datasets for use with modeling and analysis programs within Models-3.
- **Study Planner** allows you to define a study and control the execution of its associated models and processors.
- **Model Builder** allows you to prepare a model for a specific area for execution. You have the ability to select horizontal grid resolution, vertical layering resolution, and chemical mechanism, without the need for reprogramming.
- **Program Manager** allows you to register, update, and search for executable programs and/or scripts to make them available for use in defining studies within the Study Planner

component.

- Strategy Manager allows you to interactively execute the SMOKE Tool. SMOKE Tool documentation is available via the Help icon at the Strategy Manager screen.
- Tools Manager accesses a variety of administration, visualization, statistical analysis, and file conversion tools. The tools are Framework Administration (for the Models-3 Administrator), File Convertor, Text Editor, VisDriver (which provides access to Vis5d, Package for Analysis and Visualization of Environmental Data [PAVE], and DXDriver [driver for IBM Data Explorer]), ArcInfo, and Statistical Analysis System (SAS).

4.0 DEGREE OF FUNCTIONALITY PROVIDED

This section provides a list of software changes since the last release, any assumptions or limitations of the Models-3 framework broken down by Models-3 component, and any problems found during testing of the released version.

4.1 Changes Since Last Release

A significant change in this release from the last release is the replacement of the Models-3 Emission Processing and Projection System (MEPPS) model and the Models-3 Emissions Projection (MEPRO) model with the Sparse Matrix Operator Kernel Emission (SMOKE), and the addition of an input processor for SMOKE called SMOKE Tool. The Inventory Data Analyzer (IDA) was deleted in this release as the needed functionality is now included in SMOKE Tool. Changes are included in various Models-3 framework components to accommodate SMOKE and SMOKE Tool; these changes are described in Section 2.0 of Appendix A (SMOKE Tool Documentation). Other changes were also made to correct operational problems, and they are described in the following sections.

4.1.1 Data Base

SMOKE and SMOKE Tool programs were registered into the data base, a SMOKE tutorial study (smkplans_tut36) was added to the data base, and a set of data files (including revised inventories) were included in the release to run the smkplans_tut36 study. The revised inventory files are:

•	area/arinv.tut36.ida.txt	Area source inventory file
•	point/pt.inv.tut36.txt	Point source inventory file
•	point/psplit.tut36.txt	Stack split stack file
•	point/pgroup.tut.36.txt	Stack split stack group file

4.1.2 Presenter

Numerous updates were made to make the graphical interface more robust.

4.1.3 Study Planner

Changes were made to accommodate the addition of the SMOKE model. See Appendix A.

4.1.4 Science Manager

No changes for this release.

4.1.5 Model Builder

A new version of CHEMMECH is included in this release replacing the previous version. The new version adds a new variable, MECHNAME, as a parameter declaration to the mechanism COMMON include file – RXCM.EXT.

4.1.6 Tools Manager

The File Convertor tool has been revamped. The processor that does Input/Output Application Programming Interface (I/O API) to I/O API, I/O API to ASCII, and ASCII to I/O API conversions was rewritten. It is far more efficient than the previous processor. Conversions from I/O API to SAS format and SAS to I/O API must be done as a two-step process by the user – I/O API to ASCII then ASCII to SAS, or if going the other direction, SAS to ASCII then ASCII to I/O API. The important thing to remember when going from ASCII to I/O API is that the user must click the *Selection* button, then enter information required by the I/O API file header (i.e., Start Date and Time, End Date and Time, Number of Layers, Number of Rows, and Number of Columns).

4.1.7 SMOKE, SMOKE Tool, MEPPS, MEPRO and IDA

MEPPS was removed and replaced by SMOKE. IDA was also removed as the functions needed for SMOKE are incorporated in the added SMOKE Tool. The MEPRO model was removed as SMOKE includes an emissions projection capability.

Information on the installation and use of the SMOKE system and its utilities with Models-3 may be found either in the on-line SMOKE Users Guide (M. R. Houyoux, J. M. Vukovich, and J. E. Brandmeyer, 2001), or in the same document in pdf format contained in the tar (compressed) file containing the SMOKE code. These are maintained by the SMOKE developer, MCNC North Carolina Supercomputing Center, on the internet at http://iceis.mcnc.org/.

SMOKE Tool has four basic functions:

- Emission Chemical Mechanism Preparation.
- Emission Inventory Preparation.
- SMOKE Input File Preparation.
- Grid Spatial Surrogate Preparation.

The main SMOKE Tool screen, accessed via the Models-3 Strategy Manager, starts the first three functions. Individual functions within the SMOKE Tool have the ability to register datasets produced with the Models-3 Dataset Manager. SMOKE Tool documentation is included in this document as Appendix A. Grid Spatial Surrogate Preparation is executed in batch mode via one or more study plans registered using the Models-3 Study Planner. Grid Spatial Surrogate Preparation is included in Appendix A. The SMOKE Tool documentation in Appendix A is accessible in Models-3 Version 4.1 by selecting the Help icon at the Strategy Manager main screen.

The land-use gridding program in SMOKE Tool creates an I/O API format file which can be used as input to BEIS3. Some users may be using BEIS2 rather than BEIS3. Therefore, a program, BEIS 3to2, was added to SMOKE Tool to convert the I/O API file to be BEIS2 readable. The user can select the I/O API files from the SMOKE Tool land-use gridding program for input to BEIS3, or the user can select the ASCII files output from the BELD3to2 SMOKE Tool program for input to BEIS2.

4.2 Assumptions, Limitations, and Problems

The following paragraphs present assumptions, limitations, and problems with various Models-3 components.

4.2.1 Presenter

This section addresses common problems found in the graphical interface of the Models-3 framework.

- If you have selected a remote host that has been registered as Orbix-enabled but Orbix is not running, problems can occur, and the Models-3 framework may crash.
- The print function will not work properly in certain complex windows. The problem appears in the Galaxy libraries. No immediate action is planned to remedy the problem.
- Every object (e.g., dataset, program, etc.) has a unique identification (ID) that you normally would not need to know. However, when uniqueness is required, the ID can assist you in distinguishing among different objects with the same name. You can reveal

the IDs in both the summary and detail windows. Simply enlarge the summary windows and an ID column will appear. In the detail windows, go to the menu bar, click *View*, and select *Hidden Info*. An informational pop-up window that includes the ID will appear.

- If you exit while a save is in progress, an "object not saved" type of message appears. You should select *Cancel* and wait to avoid any problems. If the object has been saved, a "saved successfully" type of message is displayed. If you have saved an object but it has taken a while and no message has appeared, the object can be saved again.
- User Hint: Save frequently when adding or changing information. As an example, in Study Planner when annotating file links you may have many file links to annotate in a plan. A good rule of thumb is you should not annotate more than three links without doing a Save.
- On rare occasions, the Orbix daemon may get suspended when it is started directly from Unix. This is sometimes caused by Concurrent Versions System (CVS). You should always use the "m3run" script to keep this from happening.
- When an object other than a dataset is copied, the server thinks it is editing the original object. If the original object is edited before the copy is saved, the message "Someone else is editing this object" is displayed. The message can be ignored. After saving the object, the message will not appear again.
- When using the NT or X-Window emulators, the system pauses and waits for you to do something. If the mouse is moved, the system will continue. This is a problem in the Galaxy library and cannot be fixed at this time. It is important to occasionally move the mouse when long operations are occurring. This situation occurs frequently in the NT version when a node is being executed in Study Planner and it is time to update the screen. The execution does not stop, but you will not know the current status of the execution until the mouse is moved.
- Find screens will accept more than 16 characters in a Name (Dataset, Study, Plan, Program, etc.) field. Creation screens limit the names to 16 characters. The user should never enter more than 16 characters for a Name on a find screen.
- On the NT, if Models-3 is not acting normally (e.g., you are having trouble doing a Save), there is a possibility that one of the Models-3 subsystems has aborted. Exit Models-3 when this happens. Next focus on the orbix window and do a **Ctrl C**>. Then exit the two windows that were being used by Models-3, start up two new windows, and reinitiate Models-3.

4.2.2 Dataset Manager

- When selecting *Dataset/Visualize* at the menu bar of a Dataset Detail Window, a Vis5d format file is expected unless the file is in I/O API format. If the file format is I/O API, the VisDriver Program is displayed automatically. To use an I/O API format file, VisDriver from the Tools Manager can also be used.
- The *Dataset/Move* does not catch the error when you specify a file that is really the same file but different hosts were provided. (The file is mounted on both hosts.)

4.2.3 Study Planner

- On rare occasions when executing a plan, a warning message displays stating that "The Study Planner has experienced a problem and has restarted. It will no longer provide you with feedback" If this message occurs, you should click on the warning message *OK* button, select the Plan tab, then copy the selected plan (i.e., at menu bar click *Edit* > *Copy* > *Paste*), then select the New plan, click the Details icon, rename the New plan, and Save. Execution from the copy of the original plan should proceed without a problem. You should delete the original plan, and you can rename the New plan back to the original plan name.
- When copying selected nodes, datasets, or both with their connected edges from one plan to another, the edges are not correctly updated visibly on the screen when an individual node or dataset is moved. This is corrected after saving and refreshing the study.
- When clearing an environment variable that is a higher-level environment variable (i.e., a study or plan level) from the Node Properties screen, the environment variable will not be displayed when going back into the Node Properties until some other action is done (e.g., pressing *OK* on the Node pop-up then coming back in).
- You cannot get a file from, or put one to, a non-Orbix-enabled machine that does not have a "models3" user by using a data source or sink when the execution of the connected node is not done on that machine. This is because Models-3 does not have a user ID and password for that machine. A dummy node can be created on the remote machine that allows the file to be specified as the output (or input, if using as a sink).
- You cannot copy a file between two non-Orbix-enabled machines if they do not use the same ID/password.
- Models-3 will abort if the user attempts to 'Exit' a plan when there is still an active Annotate Link Properties screen for the plan. The work-around is to 'Exit' all Annotate Link Properties screens displayed for a plan before exiting the plan detail screen.

- There are five places where the execution host can be set in Models-3 that can affect a plan execution -- in program registration, at a study detail window, at a plan detail window, and when annotating file links (both 'To' and 'From') at the Define Physical File Location screen. In the Execution Host pick list selection, a user can select [Default Host] from the list and the host name is displayed within square brackets. The user can also explicitly select the same host in the list whereby the host is displayed without brackets. Be consistent in the way you select the host (i.e., default or explicit). The reason for this is Models-3 Study Planner sometimes does not recognize that the host name in square brackets assigned in one place is the same as the same host name assigned without the square brackets. Being inconsistent can cause Study Planner to hang in execution, overwrite a file (Unix platform), attempt to write to the wrong drive (NT platform), or cause Models-3 to request the user to enter a password. An additional measure of protection against overwriting files should also be taken by making static input files (e.g., CEM data and inventory files) to not have write permission.
- **User Hint**: In Study Planner, when annotating an input file link at the Link Information screen, there is a 'From' link and a 'To' link (below the 'From' link). If using the pick lists to select the files, select the 'To' pick list button before the 'From' pick list button to view the list of input logical file names specified for the program assigned to the node.
- **User Hint:** In Study Planner, when annotating physical file links, use the 'Physical File' pick list button then select 'Filter' at the Select File window. By using the filtering capability to establish a file path and name instead of typing them in, you eliminate the possibility of a typographical error.

4.2.4 Strategy Manager

There are no known problems.

4.2.5 Program Manager

• A physical file is not deleted when delete is selected. By design, only the metadata is deleted.

4.2.6 Science Manager

- If data is entered for the horizontal grid specifications that do not allow the grid to be viewed, an error message is displayed in the Orbix window.
- In the Vertical Layering Detail Window, you can generate the vertical layers as many

times as you want. Once the metadata is saved, you cannot change the vertical layering type or regenerate the vertical layers. However, you can add to or otherwise modify the existing vertical layers.

- When editing two horizontal coordinate systems at the same time, only one projection parameters pop-up window can be displayed at a time.
- When copying a coordinate system at the Coordinate System detail page, after selecting a coordinate system to copy, you must first click on the *Projection* button and then *Component/Copy* at the menu bar. If you do not first click on the *Projection* button, the projection parameters will not be included in the copy.
- For GridViewer to work in the NT version, an X-Window server must be on the system, and the X-Window server must have been already initiated by the user. GridViewer is the program run when *View Grid* is selected on the Grid Definition tabbed page of the Horizontal Grid Manager.

4.2.7 Model Builder

- When you do a Model Build, the system issues a "The model has been generated" message when the build execution completes. The system does not determine, though, if errors were in the build itself. You should click the *View Build Log* and *View Compile Log* buttons after the message is issued to be sure that no errors are in the logs.
- **Note:** Model Builder is not implemented for the Cray computer.

4.2.8 Tools Manager

• In order to bring up VisDriver on NT, both Interix and an X-Window server must be on the system, and the X-Window server must have been already initiated by the user.

4.2.9 Execution Manager

There are no known problems.

4.2.10 File Migrator

- For File Migrator to function best, there should be a "models3" user on all Unix systems. Also, the M3TEMP directory should be a mounted directory if using a machine other than the one the servers are on.
- Remember that to function properly on Unix systems, the .rhosts file of each user of any

non-Orbix-enabled machine must allow access to both the user and the machine that is running the File Migrator. Please refer to the *System Installation and Operation Manual* for the EPA Third-Generation Air Quality Modeling System (Models-3 Version 4.1 for Sun Unix and NT) for more instructions.

4.2.11 Help

- Help is displayed through an Internet browser. Your system must have a default browser installed to see Help. Also, the browser must take a command line argument. If the browser is already started, the system will not "un-iconize" it and bring it to the front.
- *Index* and *Tutorial* from the Help pull-down menu are not implemented.

4.2.12 File Convertor

- When using free format and specifying a Fw.d format, the w (width) is ignored, and the display for a value less than 1 is 0.xx with d decimal accuracy.
- Free format using a blank delimiter has been changed to process multiple blanks as one delimiter.
- **Note:** File Convertor has the ability to do simple units conversions where the conversions are a multiplicative factor. By design it does not have the ability to do conversions where more than just a multiplicative factor is involved [e.g., C = 5/9 (F 32)]. Therefore, in File Convertor at the Describe Variable screen, you will not find 'Temperature' in the Category pick list. File Convertor does not have the ability to convert between different temperature scales.
- The process of converting between SAS format and I/O API format files described in the Models-3 user manual no longer applies. The way to convert between SAS and I/O API files is a two step process. Do one run converting from I/O API (or SAS) to ASCII, and then do a second run converting from ASCII to SAS (or I/O API).
- I/O API files have a header containing temporal, gridding, and vertical layering information. To do an ASCII to I/O API or I/O API to I/O API file conversion, this information is entered via the Select Criteria screen accessed by clicking the *Selection* button at the File Convertor main screen.

5.0 INSTALLATION INSTRUCTIONS

Please refer to System Installation and Operation Manual for the EPA Third-Generation Air Quality Modeling System (Models-3 Version 4.1 for a PC NT Operating System).

APPENDIX F-1 SMOKE TOOL DOCUMENTATION

CONTENTS

1. SMOKE Tool	F-21
2. Grid Spatial Surrogate Preparation	F-21
3. Grid Directories	F-23
4. SMOKE Input File Generation	F-24
5. Study Planner	F-24
6. Grid Information	F-24
7. Case Information	F-25
8. Chemical Mechanism Information	F-25
9. Extracting CEM Data for Case	F-25

1. SMOKE TOOL

The SMOKE Tool is an input processor for SMOKE, executed in part via Strategy Manager. The tool has four basic functions:

- Emission Chemical Mechanism Preparation.
- Emission Inventory Preparation.
- SMOKE Input File Preparation.
- Grid Spatial Surrogate Preparation.

2. Grid Spatial Surrogate Preparation

The primary purpose of the grid processor is to generate spatial surrogates for SMOKE horizontal gridding. The grid processor is executed through nodes in a study plan. The underlying functions that the grid processor executes are modified versions of the Statistical Analysis System (SAS) and ArcInfo gridding programs copied from the MEPPS Emission Processor (EMPRO). The grid processor performs the following functions:

•	Define Grid	Creates the	grid works	pace, receiving th	ne grid descr	iption file from

the Study Planner. The program creates the grid directories, imports the grid description, and generates the base Geographic Information System (GIS) coverages in the workspace. The grid description is read from file G_GRIDPATH (supplied from the

study planner).

• Generate Coverages Generates GIS coverages in the workspace. The user selects the

coverages to generate through environment variables. The names of the environment variables are based upon the GIS coverages

defined to the SMOKE Tool.

• Generate Surrogates Computes spatial surrogates for the grid from the GIS coverages

generated for the grid. The user selects the coverages to include in the surrogate calculation through environment variables. The program computes all spatial surrogates defined for each coverage

selected.

The grid processor creates the grid directories in a user-specified location. The location is specified through the following environment variables:

• EMS_HOME Workspace Path. The base directory under which the grid

information is stored. Supplied by user.

• HGRIDNAME Models-3 Grid Name. The grid name is used to define

subdirectories under the workspace path for the grid. Supplied by

Study Planner.

All data for the grid, created by the Define Grid and Generate Coverages functions, is stored in subdirectories under directory **\$EMS_HOME/gridspec/\$HGRIDNAME**. The user specifies the location of the spatial surrogate file, created by the Generate Surrogate function, in a plan output file specification.

The user defines the GIS coverages available to SMOKETOOL through the following environment variables:

• GISDB Name of the GIS data base directory. This directory

contains the GIS coverages and related data files for the

surrogate processing.

• COVER DEF Name of the file containing the coverage definition table.

This table defines the GIS coverages available for surrogate

processing.

The initial GIS coverages released with Models-3 are:

•	COUNTY	County areas
---	--------	--------------

•	CENSUS	Census tract/block group areas	(US only)
•	FHAROAD	FHA road lengths	(US only)
•	AGRICULTURE	Agricultural areas	(US only)

AIRPORTS Airport locations
 PORTS Port locations
 RAILROADS Railroad lines
 LAND_WATER Land-water areas
 URBAN-RURAL Urban-rural areas
 ROADS Road lengths
 FOREST Forest areas

• TIGER TIGER/Line roads (US only)

To select a coverage, set the environment variable for the coverage to YES or Y. The value may contain upper or lower case letters. Sample environment variable settings that cause coverages to be processed are:

PORTS=Y AIRPORTS=YES RAILROADS=yes

The surrogates step also uses the following environment variables:

- FEATURE_SRG Name of the Feature-Surrogate Table. This table defines the manner in which spatial surrogates are computed from the coverage features.
- CENSUS_DATA Name of the Census Data File. This file contains housing and population data associated with the CENSUS coverage. It may also contain state or county level data.
- FEAT_STCY_FRAC Name of the Census State-County Fraction table. This file contains fractions to allocate state level census data to the counties within the states.
- SURROGATES Name of the spatial surrogates file. This contains the spatial surrogates (or gridding coefficients) computed in the surrogates step.

The follow sections describe the various directories, GIS coverages, and files used in the spatial surrogate processor.

3. Grid Directories

The grid master directory is **\$EMS_HOME/gridspec/\$EMS_GRID**. The subdirectories created are shown in the following table:

<u>Subdirectory</u>	Type of Data	Environment Variable	SAS Reference
common/sas	Ungridded Emissions	EMS EMS_CVRT	library EMS file EMS_CVRT
common/gis	Ungridded GIS	EMSG	file EMSG
sas	Gridded Emissions	EMS_GRD EMSF_GRD	library EMS_GRD file EMSF_GRD
gis	Gridded GIS	EMSG_GRD	file EMSG_GRD

The first two directories contain data for the grid's geographic area that have not been processed for a grid. The EMSG directory contains GIS coverages that have not been overlaid with a grid.

The gridded data directories contain data that have been processed for the grid. EMS_GRD contains the grid description and gridded data files. The EMSG_GRD directory contains GIS coverages that have been overlaid with the grid.

4. SMOKE Input File Generation

The SMOKE Tool generates the following input files for SMOKE:

- Temporal Profiles.
- Temporal Cross-References.
- Gridding Cross-References.
- Area and Point Source Control Files.
- Speciation Cross-References.
- Pollutant File (SIPOLS).
- MOBILE Emission Factor Cross-Reference (MPLIST).

SAS is used to generate the input files for SMOKE. The individual files contain a number of packets. Each packet contains a set of different fixed-format records. SAS routines are used for data checking, sorting, and merging the packet data into the full files.

Some additional files that are not handled in the tool are the ACTRACK, PCTRACK, and MPREF files. The ACTRACK and PCTRACK files identify sources to include in the control reports. These are simple, free-form ASCII files that list the counties and Source Classification Codes (SCC) for the report. Screens could have been generated to input these lists, but it is simpler for the user to type the lists directly and annotate the report node with the file name. The MPREF file defines the MOBILE5 inputs for SMOKE. It contains the statements that define SMOKE emission factor sets and imbedded MOBILE5 input statements.

The following sections describe the files processed in the SMOKE input processor of the SMOKE Tool. In most cases the tool allows the users to load pre-existing data, modify the data, check the packet data for data value errors, and cross-check the data in different packets.

5. Study Planner

Changes were made to the Study Planner to get the necessary information to SMOKE. The information that SMOKE must get at the time of the execution of the program is:

- Grid Information (including horizontal grid, coordinate, and vertical layer information).
- Case Information.
- Chemical Mechanism Information.
- Extracted Continuous Emission Monitoring (CEM) Data for Case.
- File Lists for SMOKE Input.

6. Grid Information

In the past, Study Planner did not allow selection of grid information because Model Builder compiled the grid information directly into the FORTRAN code. This caused the program to require compiling every time the grid was changed. To implement SMOKE and other programs so that the executables do not require recompiling every time, the grid information from the Science Manager was made available to the SMOKE program.

7. Case Information

Currently, Study Planner sends the case information in environment variables. There are four environment variables as follows:

- G_STDATE Julian Date in YYYYDDD format.
- G_STTIME Time in HHMMSS format.
- G_TSTEP Time step in HHMMSS format.
- G RUNLEN Run length in HHMMSS format.

YYYY is the four-digit year. DDD is the number of days since the beginning of the year. HH is the hours (this does not have to be two digits; it can be any number of digits). MM is the minutes (two digits). SS is the seconds (two digits).

8. Chemical Mechanism Information

Chemical mechanism information is passed to SMOKE as it is executed in Study Planner. This is done using the same idea discussed in Section 2.1, Grid Information. The files are created, and environment variables provide the location of these files. In addition, CHEMMECH outputs the RXCM.EXT and RXDT.EXT files into one file in the same format as was discussed in Section 2.1. The environment variable name is C_RX for the file created by CHEMMECH and C_TABLE for the remaining chemical mechanism files. The chemical mechanism is a selection at the study and plan levels.

9. Extracting CEM Data for Case

A specific SAS program was developed and is executed as a node in a plan. The program has two inputs:

- The Models-3 case description annotated to the node via environment variables G_STDATE, G_STTIME, and G_RUNLEN.
- A CEM dataset (SAS) specified through an input link. The user has to annotate the link, selecting a registered CEM dataset that contains data for the case period.