

3. DATABASE USER'S GUIDE

3.1 Assumptions

This guide to using the database assumes a basic knowledge of computer database management software. Skills needed to navigate the database include the ability to browse database tables, to link multiple tables in a database query, and to apply simple logic in a database query for extracting the appropriate information. The database was developed in the PC-based Paradox™ 4.0 database management system but may be used in other relational database management packages provided they are compatible with the electronic file formats. Database files are provided on CD-ROM in two formats, the original Paradox™ 4.0 format and a FoxPro™/dBase III™ format. Comprehensive documentation of electronic files is provided in this chapter, including field definitions for database tables and diagrams of database linkages. Practical examples for common queries and applications of the database are provided in this chapter.

3.2 Data Dictionaries and Glossaries

Data dictionaries for all database tables are provided in this report. The data dictionaries are grouped by directory and subdirectory. Each set of directory and/or subdirectory data dictionaries is preceded by a table listing data dictionaries contained within. The database contains more than 100 tables; refer to the list of tables given in the table of contents. As this chapter touches on each of the database components, the reader will be referred to the relevant data dictionaries. The glossaries which define the terms of the database are contained in the database itself. (See Figure 2-2 for files coded with an asterisk).

3.3 Using the Data

A theme common to nearly all components of the TAMS/Gradient Hudson River database is the notion of the *one-to-many* relationship. Simply put, a *one-to-many* relationship exists when a single record or row in one database table links to many records in another database table. This design suits the nature of monitoring data because often multiple parameters are associated with a single sampling location. Figure 3-1 shows an example of *one-to-many* relationships from the PHASE2\HRCORES subdirectory. In the center is the **STATIONS** table where one record representing a single sampling location is linked, not only to many records in the **PCBS** table containing the congener results, but also to many records in the **NONPCBS** table containing conventional or non-PCB results. Each table is linked by the **TAMS ID** and **TAMS Type** fields. This figure illustrates the basic building block in the database design, and understanding the approach described will assist the reader in properly applying data analysis to the database. Specific details inherent to each data set vary among directories and are covered below.

The remainder of Section 3-3 discusses the individual data directories and the relationships among the database tables. Each directory is represented in a figure showing these relationships. In these figures, rectangles are used to distinguish reference tables; circles denote

tables which provide sample definitions; diamonds represent tables which contain analytical and field data. The sizes of these shapes are varied to emphasize the main database tables. The main database tables are emphasized in the larger circles and diamonds.

3.3.1 Historical Data

Table 3-1 describes the look-up table **HIST_LUT** in the *HISTORIC* directory. The **HIST_LUT** table is a glossary for the database parameters and fields contained in the databases of the *HISTORIC* directory. In addition, Table 3-2 describes the **PARAMKEY** table in the *HISTORIC* directory. The **PARAMKEY** table provides a parameter key for the **GE89** table under the *HISTORIC\SED* subdirectory and the **CONCFISH** table in the *HISTORIC\FISH* subdirectory.

Sediment Data

In the historical sediment subdirectory, there are more than 4,700 samples for the period 1976 through 1990. Figure 3-2 shows how the tables in the *HISTORIC\SED* subdirectory are linked. A listing of the database tables follows, and is also provided in Table 3-3. Database table field definitions are given in Tables 3-4 through 3-16.

Tables in *HISTORIC\SED* Subdirectory

Table Name	Description
SAMPLES	Sediment sampling information NYSDEC/OBG (1976-1978) NYSDEC/NYSDOH (1984-1985) GE/Harza (1990)
STATIONS	Station number correspondence to GradNo (a unique sample identifier for database purposes)
GRADNUMS	Core section correspondence to GradNo sample identifier
SECTION	Section number, depths, and correspondence to GradNo sample identifier
REACHES	River reach numbers
CONCSED	PCB Aroclor data - sediment samples
NONCHEM	Non-PCB data - sediment samples
SOXHDUP	Duplicate PCB Aroclor data using soxhlet extraction
NONDETS	Key to non-detected qualifier codes
REF	Key to references used in building the database
TEXTURES	Sediment description key

Tables in *HISTORIC\SED* Subdirectory (Continued)

Table Name	Description
GE89	Preliminary 1989 GE sediment baseline studies GE/Harza (1989)
MASSPEC	Results for GC/MS performed for sediments collected during 1984-1985 NYSDEC survey of Upper Hudson

As an illustration of the database format, excerpts from the main sediment database tables are summarized below in four tables. Each of these tables is linked by a unique sample identification number (**GradNo**), *e.g.*, 30000, 30016, 30032 and 30208 shown here.

The **SAMPLES** table contains information including sample date, location (River Mile, distance from bank, and northing and easting coordinates, where available), sample type (grab versus core), water depth, surface elevation, and type of sampler used. The table below provides example records, although precise field names have been expanded from their abbreviations so that the reader need not refer to the field definitions.

Excerpt from the Sample Information Table (SAMPLES)

GradNo	Type	M/D/YR	River Mile	Feet from West Bank	Northing (ft)	Easting (ft)	Sampler	Water Depth (ft)	Elev (ft)
30000	Grab	5/21/77	168.8	330.05	1071755	685695	100		
.									
30016	Core	3/18/77	188.4	100.0	1163740	698970	100	5.8	119.6
.									
30032	Core	3/18/77	183.4	60.0	1140410	669040	100	2.2	102.4
.									
30208	Core	6/6/78	192.5		1182860	696350	40	7.0	119.2

Core samples in the **SAMPLES** table are linked by **GradNo** with the core section (**SECTION**) table, which identifies the length of each core sample section and the depth beneath

TAMS/*Gradient*

the river bottom, *i.e.*, the interval of sample penetration given by the top and bottom of each section. Only core sample IDs appear in the **SECTION** table and many sections are associated with a single sampling location. No grab sample IDs appear in the **SECTION** table because no depth intervals are associated with them.

Excerpt from the Core Section Table (SECTION)

GradNo	Core Section No.	Bottom of Section (in)	Top of Section (in)
30016	1	1	0
30016	2	2	1
.			
30016	12	12	11
.			
30208	1	6	0
30208	2	9.5	6
30208	3	12	9.5

Most database queries involve linking **SAMPLES** (and **SECTION**, for cores) to the main database table containing the PCB results, **CONCSED**. Selecting a **GradNo** from **SAMPLES** and **SECTION** and locating the same **GradNo** in the **CONCSED** data table shows either the Aroclor results for an entire grab sample or section-by-section results for core samples. Additional information describing analytical measurement methods, that is, extraction method, are contained in the database as available.

Excerpt from the Chemical Data Table (CONCSED)

GradNo	Parameter	Core Section No.	Extraction Method	Concentration (ppm)
30000	Aroclor 1016		shake	1.0
30000	Aroclor 1221		shake	1.0
30000	Aroclor 1254		shake	1.0
30016	Aroclor 1016	4	soxhlet	6.0
.				

TAMS/*Gradient*

GradNo	Parameter	Core Section No.	Extraction Method	Concentration (ppm)
.				
30016	Aroclor 1254	12	soxhlet	0.1
30032	Aroclor 1016	5	soxhlet	234.0
.				
30032	Aroclor 1254	5	soxhlet	163.0

Finally, non-chemical data, such as sediment texture class and percent volatile versus total solids, are contained in the **NONCHEM** table. **SAMPLES** is linked to **NONCHEM** through the **GradNo**. The same IDs for the example records for the previous tables are shown.

Excerpt from the Non-Chemical Data Table (NONCHEM)

GradNo	Core Section No.	Parameter	Value
30000		% total solids	78.93
30000		% volatile solids	0.85
30016	1	texture	GRAVEL
30016	4	% total solids	85.97
30016	4	% volatile solids	2.2
.			
30016	12	% total solids	89.23
30032	1	texture	CL-WC
.			

TAMS/Gradient

30032	5	% volatile solids	25.39
-------	---	-------------------	-------

The remaining database tables provide reference information for the main database tables. **STATIONS** is a two-field table that shows the correspondence between the assigned **GradNo** and the original NYSDEC or GE station number. **GRADNUMS** cross-references the Agency or investigator who collected the data and is linked back to **SAMPLES** and **REF**. Duplicate PCB measurements made using soxhlet extraction reside in a side table called **SOXHDUP**. The key to non-detected data qualifier codes is given in **NONDETS**. **REACHES** indicates the upstream and downstream river miles associated with river reach numbers for the Upper Hudson River. The last table in the *HISTORIC\SED* subdirectory, **GE89**, holds the preliminary 1989 GE baseline studies results separate from the other database tables.

Fish Data

Figure 3-3 shows how the database tables contained in the *HISTORIC\FISH* subdirectory are linked. Table 3-17 and the table below describe the contents of each database table. Tables 3-18 through 3-25 explain field names and types in more detail. Results for over 10,000 samples collected from 1973 through 1993 are available in three main database tables: **GRADNUMF**, **SAMPLEF**, and **CONCFISH**. These three tables accommodate most database queries. **GRADNUMF** provides the master index to sample IDs (**GradNo**) and the corresponding original NYSDEC sample identifiers: laboratory number (**Labno**) and sample tag identifier (**Tagno**). **SAMPLEF** is similar to the **SAMPLES** table found in the *HISTORIC\SED* subdirectory and contains sampling information such as location descriptor, river mile, sampling date, species and preparation code. If a sample is composed of more than one individual fish, there will be a number greater than 1 in the **Noincomp** field (number of fish in composite) and a record in the **COMPOS** table connecting sample group weight and length statistics to the sample record. **SAMPLEF** is linked to the data table with all the PCB Aroclor and percent lipid results called **CONCFISH** through the sample ID (**GradNo**). The four tables, **PARAMKEY**, **PREP**, **SPECCODE**, and **REF**, contain keys to parameter codes, preparation codes, species codes and references, respectively, used in building the database. Finally, the **CORRNUM** table identifies corresponding old and new sample identifiers which have changed for some samples between the Phase 1 Report and this Report.

Tables in *HISTORIC\FISH* Subdirectory

Table Name	Description
GRADNUMF	Master index to GradNo
SAMPLEF	Fish sampling information (location, sex, age.....)
CORRNUM	Correspondence between old and new GradNo
COMPOS	Sample information for composite samples
CONCFISH	PCB Aroclor and percent lipid data - fish samples
PREP	Key to tissue and preparation codes
SPECCODE	Key to species codes
REF	Key to references used in building the database

Macroinvertebrate Data

Some macroinvertebrate data are available in the *HISTORIC\MACROINV* subdirectory. Figure 3-4 shows the database table relationships. The contents of each table are described below and in Table 3-26, while Tables 3-27 through 3-33 define the database fields. The macroinvertebrate sampling information in **SAMPLE** is linked through the sample ID field, **GradNo**, to the **CONC** table which contains the PCB Aroclor measurements. Species codes, sample type codes, and the number of individuals per sample are given in **SPECCODE**, **SAMPREF** and **NUMINDI**, respectively. There are approximately 800 samples but not all species could be identified based on the original documentation. **DOHSITE** contains multiplate and caddisfly sampling location information.

Tables in *HISTORIC\MACROINV* Subdirectory

Table Name	Description
SAMPLE	Macroinvertebrate sampling information
SAMPREF	Key to sample type
NUMINDI	Number of individuals in samples
CONC	PCB Aroclor results
OTHER	Additional species included in samples
SPECCODE	Species codes
DOHSITE	Multiple and caddisfly sampling information

3.3.2 Lamont-Doherty Earth Observatory

The *LDEO* directory contains four self-descriptive spreadsheet tables which provide several sediment core results as well as a PCB sediment/water partitioning study.

3.3.3 USGS

The database glossary for field names and parameters contained in the database tables under *FLOW* and *WQDATA* subdirectories is provided in the look-up table **USGS_LUT** in the USGS directory (See Table 3-34). A listing of the database tables follows, and is also provided in Tables 3-35 and 3-37. Database table field definitions are given in Tables 3-36 for *USGS\FLOW* and 3-38 and 3-39 for *USGS\WQDATA*.

Tables in *USGS\FLOW* Subdirectory

Table Name	Description
FTEDWD	Mean daily Hudson River flow at Fort Edward, 1976-1993
GREEN	Mean daily Hudson River flow at Green Island, 1946-1993
HADLEY	Mean daily Hudson River flow at Hadley, 1921-1993
CORINTH	Mean daily Hudson River flow below Sacandaga River near Corinth, 1921-1993
SCHU	Mean daily Hudson River flow at Schuylerville, 1977-1979
STILL	Mean daily Hudson River flow at Stillwater, 1977-1993

TAMS/Gradient

Tables in *USGS\FLOW* Subdirectory (Continued)

Table Name	Description
WATR	Mean daily Hudson River flow at Waterford, 1976-1993
BATK	Mean daily Batten Kill flow at Battenville, 1922-1968
HOOS	Mean daily Hoosic River flow near Eagle Bridge, 1910-1993
SACAND	Mean daily Sacandaga River flow at Stewarts Bridge, 1907-1993
MOHK	Mean daily Mohawk River flow, 1917-1993
USGS7693	Mean daily flow at all above stations, except Battenville, 1976-1993

The *USGS\FLOW* subdirectory includes USGS mean daily flow data in cubic feet per second collected at various stations.

Tables in *USGS\WQDATA* Subdirectory

Table Name	Description
USGSWQ	Water-column PCB, suspended sediment data, and sediment load, in tons/day, collected by the USGS
TOCDAT	Water-column total organic carbon (TOC) collected by the USGS

The *USGS\WQDATA* subdirectory includes water column PCB, total suspended sediment data, and sediment load in tons/day in **USGSWQ** and water column total organic carbon data in **TOCDAT**.

3.3.4 GE Data

The TAMS/Gradient team received data for over 2,000 samples from GE in several files, the most recent being GE081895.DBF and CP081895.DBF received in August 1995. The former file contains all the field sampling information, the homologue distributions, and the total PCB measurements for all sampling surveys combined. The latter contains the congener concentrations for all sampling surveys combined. The results have been divided into five main database tables with one reference table and three glossaries as shown below as well as in Table 3-40 and Figure 3-5. Data dictionaries for tables contained in *GE* are provided in Tables 3-41 through 3-49.

Tables in *GE* Directory

Table Name	Description
SAMPLE	Sampling information for all GE data contained in this directory
PCB	PCB data for all media
PCBHOMOL	PCB homologue data for all media
PCBCONG	PCB congener data for all media
NONPCB	Non-PCB data for all media
SPECCODE	Fish species code
PCB_LUT	Congener data glossary
GEPARAMS	Parameter abbreviations glossary
FIELD_LUT	Database field glossary

Sampling information such as sample date, location and medium (*e.g.*, water, sediment or biota) reside in the table **SAMPLE**. Samples for all matrices were assembled into a single **SAMPLE** table and hence not all the fields pertain to every record. For instance, **Age** applies only to biota or fish samples and not to sediment, water or pore water samples. Where a field does not apply, the entry remains blank or contains a "0" as a placeholder. The **SAMPLE** table is linked to all the PCB and non-PCB results through the **NEA_file** identifier. Total PCB values, qualifiers, and quantitation limits are given in **PCB** for all media. Homologue distributions by mole percent and by weight percent are given in **PCBHOMOL** for all media. Congener concentrations are given in **PCBCONG** for all media. It appears that GE reported non-detected congeners as "0" in **PCBCONG**. **NONPCB** holds all conventional parameters, such as total suspended solids and total organic carbon, with abbreviations explained in **GEPARAMS**. A key to the congener peak numbers is provided in **PCB_LUT** which also gives a corresponding BZ number to relate these results to those being analyzed under the Phase 2 sampling programs.

3.3.5 New York State Department of Transportation

The **NYSDOT** directory contains the table **GAUGES** which provides the readings of staff gauges listed in Table 3-50.

3.3.6 Phase 2 Data

Database glossaries **CONG_LUT**, **FIELDS**, **PARAMS** and **QUALIFY** in the *PHASE2* directory are described in Tables 3-51 to 3-54 and serve as keys to congener, field name parameter and qualifier definitions, respectively, for tables in the *PHASE2* directory. Data dictionaries for **AROCLSTD** and **ASCREEN** are presented in Tables 3-55 and 3-56,

TAMS/*Gradient*

respectively.

Water Column Study Data

The *PHASE2\WATER* subdirectory combines the results from the water column transects, flow-averaged events, and PCB equilibration study under the Phase 2 sampling effort. The relationships between the main database tables, *i.e.*, **GROUPS**, **STATIONS**, **PCBW**, **PCBP**, and **NONPCBW**, are shown in Figure 3-6. All tables in the subdirectory are listed below and in Table 3-57, and field definitions are given in Tables 3-58 through 3-64.

Listing of Tables in *PHASE2\WATER* Subdirectory (including Tables in *PHASE2\WATER\QA_QC* and *PHASE2\WATER\EQUILIB*)

Table Name	Description
STATIONS	Water column transects and flow-averaged events stations
GROUPS	Sample groupings
PCBP	PCB congeners/homologue sums/Aroclor concentrations - particulate samples (g/Kg)
PCBPD	PCB congeners - particulate duplicate pairs (g/Kg)
PCBPE	PCB congener - particulate samples - equilibrium study (g/Kg)
PCBFA7	PCB congeners/homologue sums/Aroclor concentrations - combined particulate and dissolved samples (ng/l) for flow-averaged event 7
PCBW	PCB congeners/homologue sums/Aroclor sums - water samples (ng/L)
PCBWD	PCB congeners - water duplicate pairs (ng/L)
PCBWE	PCB congeners - water (dissolved) samples - equilibration study (ng/L)
PCBWTT	PCB congeners - whole water samples (TT series) (ng/L)
NONPCBW	Non-PCB data - water column samples
NONPCBWD	Non-PCB data - water duplicate sample pairs
FB	Non-PCB data - field blanks
VOLUMES	Sample volumes filtered for PCB analyses

The **STATIONS** table contains sampling information such as the transect or flow-averaged event number, station number, sample identifier and type, river mile, and northing and easting coordinates where known. The sampling stations are associated with distinct zones in the river identified in **GROUPS**. **STATIONS** is linked to the six PCB data tables, *i.e.*, **PCBP**, **PCBW**,

PCBPE, **PCBWE**, **PCBFA7** and **PCBWTT**, through the **TAMS ID** and **TAMS Type** fields. Because congener results from the various efforts are so distinct (*e.g.*, sampling method or matrix), the TAMS/Gradient team felt it necessary to divide the data into separate tables to prevent mixing of data types.

PCBP and **PCBW** contain particulate and "dissolved" (*i.e.*, filtered water) PCB congener data, respectively, for the water column transects and the flow-averaged events. While duplicate pairs have been removed from the main database tables to **PCBPD**, for particulate or suspended-matter data, and **PCBWD** for dissolved-phase data, composited results following the method described in Chapter 2 have been returned to the main database tables, *i.e.*, **PCBP** and **PCBW**. The data in **PCBP** have been reported on a mass per unit mass basis, the same as the Phase 2 sediments. These values were obtained by dividing the reported results (ng/filter) by the volume filtered and the TSS value for the sample.

The results for the equilibration study are separate from the main database tables; **PCBPE** and **PCBWE** contain the equilibration study results for the particulate and dissolved fractions, respectively. A few whole-water PCB congener analyses were performed on samples taken for Transect 1 and the results reside in **PCBWTT**. Non-PCB measurements such as total suspended solids (TSS), dissolved organic carbon (DOC), and chlorophyll-*a* are given in **NONPCBW**.

As is the case with the PCB congener data, duplicate pairs have been placed in a supplementary table **NONPCBWD** with composited results placed in **NONPCBW**. Minor tables in this subdirectory include **FB**, which contains non-PCB data field blanks, and **VOLUMES**, which indicates the volume of water sample filtered for PCB analyses.

Sediment

The method for linking database tables in the *PHASE2\SEDIMENT* subdirectory is given in Figure 3-7. A listing of all tables in the *PHASE2\SEDIMENT* subdirectory is given below and in Table 3-65, while data dictionaries are given in Tables 3-66 through 3-73.

Tables in *PHASE2\SEDIMENT* Subdirectory (including Tables in *PHASE2\SEDIMENT\QA_QC*)

Name	Description
STATIONS	Confirmatory samples and low-resolution core sampling stations
PCBS	PCB congeners/homologue sums - sediment samples (1g/Kg DW) - low-resolution samples only
PCBSD	PCB congeners - sediment samples pairs (1g/Kg DW)

TAMS/Gradient

Tables in *PHASE2\SEDIMENT* Subdirectory (Continued)

Name	Description
NONPCBS	Non-PCB data - sediment samples
NONPCBSD	Non-PCB data - duplicate sediment sample pairs
FB	Non-PCB data - field blanks
SIEVEGS	Grain size distribution data by sieve analysis
SIEVEGSD	Grain size distribution data by sieve analysis - sample duplicates
LASERGS	Grain size distribution data by laser particle analysis
LASERGSD	Grain size distribution data by laser particle analysis - sample duplicates
RADNUC	Radionuclide data - sediment samples - low-resolution only
RADNUCD	Radionuclide data - sediment samples field splits and laboratory duplicates
LRINFO	Supplemental information for low-resolution core samples only
SEDDESC	Descriptive sediment classifications, density, redox and other field data

As in the *PHASE2\WATER* subdirectory, a **STATIONS** table establishes the sampling locations either by river mile or by northing and easting pairs. The core depth interval for each sample is also indicated in this table. It was not necessary to break PCB congener results into multiple tables, as was the case for the water column study. **PCBS** holds all the PCB congener results including composited duplicate samples as described in Chapter 2. The original duplicate pairs are retained in **PCBSD**. **PCBS** and **PCBSD** are linked back to **STATIONS** through the **TAMS ID** and **TAMS Type**. No other PCB tables are included in this directory because only a single matrix (sediment) was sampled. Note that these tables do not contain results for the high-resolution coring study, which are given in the *PHASE2\HRCORES* subdirectory.

The tables **NONPCBS** and **NONPCBSD** contain all the non-PCB results including total carbon, total nitrogen, total inorganic carbon, total organic nitrogen, the C:N ratio, and summary grain size analyses in sediments. Again, **NONPCBSD** holds all the duplicate pairs, while **NONPCBS** holds composited duplicate results, and **FB** holds the field blank results. Radionuclide data generated for these samples required some additional fields not needed for the other data tables, such as **Detector**, for detector type, and **Sigma**, for the standard deviation of the counting result. **RADNUC** contains all radionuclide data; **RADNUCD** contains only sediment sample duplicate data. These two tables, together with **PCBS** and **PCBSD**, contain only low-resolution sampling information. The remaining tables in this subdirectory contain information on both low-resolution and confirmatory samples. Detailed laser grain size data including composited results are contained in **LASERGS** while sample duplicates are contained in **LASERGSD**. **SEDDESC** provides descriptive sample information based largely on field

TAMS/Gradient

observations for both confirmatory and low-resolution coring samples. **LRINFO** provides information pertaining to low-resolution coring sites. Specifically, it provides the corresponding 1984 NYSDEC sediment survey station number from Brown, et. al (1988) for the coring sites located in the Thompson Island Pool. It also provides the hot spot number for low resolution coring sites below the Thompson Island Dam.

Ecological Sampling

The tables contained within the *PHASE2\ECO* directory are shown in the table below. The data dictionaries are contained in Tables 3-75 through 3-84. Figure 3-8 illustrates how the database tables are linked.

Tables in *PHASE2\ECO* Subdirectory
(including Tables in *PHASE2\ECO\QA_QC* subdirectory)

Table Name	Description
STATIONS	Ecological survey stations
COORDS	Coordinates for stations
GROUPS	Sample groupings
BENTHIC	Sample composition information - invertebrates
FISH	Sample composition information - fish
PCBFISH	PCB congeners/homologue sum/Aroclor concentrations - fish
PCBFISHD	PCB congeners - diluted fish analyses
PCBINV	PCB congeners/homologue sum/Aroclor concentrations - invertebrates
PCBINVD	PCB congeners - invertebrate dup. pairs/dilution analyses
NONPCBB	Non-PCB data - biota
NONPCBBD	Non-PCB data - biota duplicate pairs
PCBS	PCB congeners/homologue sums/Aroclor concentrations - sediment samples (̑g/Kg DW)
PCBSD	PCB congeners - sediment duplicate pairs (̑g/Kg DW)
NONPCBS	Non-PCB data - sediment samples
NONPCBSD	Non-PCB data - sediment duplicate pairs
LASERGS	Sediment laser grain size data
FB	Non-PCB data - sediment field blanks

TAMS/Gradient

Table Name	Description
SPECIES	Key to species codes
LASERGSD	Sediment laser grain size data - duplicate pairs

The **STATIONS** table, the main database table in the subdirectory, contains sampling information such as **TAMS ID**, **TAMS Type**, **Species** and location by river mile. **COORDS** is linked to **STATIONS** through the **Station** field, and contains locations by northing and easting pairs as well as sample types collected (*i.e.*, sediment, fish, benthic invertebrates). The **GROUPS** table, containing stations grouped by location, is linked to **STATIONS** in the same way. The **LASERGS** table contains grain size distribution data based on laser particle analysis on the ecological samples, and is linked to **STATIONS** via the **TAMS ID** and **TAMS Type**. **LASERGSD**, linked to **STATIONS** in the same fashion, contains information on duplicate pairs. **STATIONS** is linked to the PCB data tables **PCBS**, **PCBINV** and **PCBFISH** through the **TAMS ID**, **TAMS Type** and **Species** fields. The PCB tables, in turn, relate to the field data tables, *i.e.*, **BENTHIC** and **FISH**, through the same fields. The tables **PCBSD** and **PCBINVD**, which contain duplicate pair information, are supplementary. **PCBFISHD**, also supplementary, contains results for laboratory duplicate analyses for those samples requiring dilution. **NONPCBS** and **NONPCBB** contain all the non-PCB results for sediment samples and biota samples, respectively. Again, information about duplicate pairs can be found in **NONPCBSD** and **NONPCBBD**. These are all linked to **STATIONS** through **TAMS ID** and **TAMS Type** for sediment and **TAMS ID**, **TAMS Type** and **Species** for fish and benthic invertebrate samples. **FB** contains field blank data for ecological sampling program.

High-Resolution Cores

Figure 3-9 illustrates how tables in *PHASE2\HRCORES* are linked. A listing of tables in this subdirectory is given below and in Table 3-85. Data dictionaries are given in Tables 3-86 through 3-93.

Tables in *PHASE2\HRCORES* Subdirectory (including Tables in *PHASE2\HRCORES\QA_QC* subdirectory)

Table Name	Description
STATIONS	Confirmatory Sampling and High-Resolution Sediment Coring Program sampling stations
PCBS	PCB congeners/homologue sums/Aroclor sums - sediment samples ($\hat{1}$ g/Kg DW)
PCBSD	PCB congeners - duplicate sediment sample pairs ($\hat{1}$ g/Kg DW)
NONPCBS	Non-PCB data - sediment samples

TAMS/Gradient

Table Name	Description
NONPCBSD	Non-PCB data - duplicate sediment sample pairs
FB	Non-PCB data - field blanks
LASERGS	Laser grain size Phi classes
LASERGSD	Laser grain size Phi classes - duplicate pairs
RADNUC	Radionuclide data - sediment samples
RADNUCD	Radionuclide data - sediment sample laboratory duplicates
SEDDESC	Redox, density and additional field information
GROUPS	Sample groupings

As in the *PHASE2\WATER* subdirectory, a **STATIONS** table establishes the sampling locations either by river mile or by northing and easting pairs. The core depth interval for each sample is also indicated in this table. In the *PHASE2\HRCORES* subdirectory, sampling locations in **STATIONS** are grouped by the identifiers supplied by the table **GROUPS**. It was not necessary to break PCB congener results into multiple tables, as was the case for the water column study. **PCBS** holds all the PCB congener results including composited duplicate samples as described in Chapter 2. The original duplicate pairs are retained in **PCBSD**. **PCBS** and **PCBSD** are linked back to **STATIONS** through the **TAMS ID** and **TAMS Type**. No other PCB tables are included in this directory because only a single matrix (sediment) was sampled in the high-resolution coring study.

The tables **NONPCBS** and **NONPCBSD** contain all the non-PCB results including total carbon, total nitrogen, total inorganic carbon, total organic nitrogen, the C:N ratio, and summary grain size analyses in sediments. Again, **NONPCBSD** holds all the duplicate pairs, while **NONPCBS** holds composited duplicate results, and **FB** holds the field blank results. Radionuclide data generated for these samples required some additional fields not needed for the other data tables, such as **Detector**, for detector type, and **Sigma**, for the standard deviation of the counting result. **RADNUC** contains all radionuclide data; **RADNUCD** contains only sediment sample laboratory duplicate data. Detailed laser grain size data including composited results are contained in **LASERGS** while sample duplicates are contained in **LASERGSD**. **SEDDESC** is similar in style to a table bearing the same name in subdirectory *PHASE2\SEDIMENT* in that it contains information on redox, sediment density and other descriptive field information.

FLOW

The *PHASE2\FLOW* subdirectory contains one table, **FLOW93**, which includes calculated 1993 flow data for Stillwater and Waterford. The **FLOW93** data dictionary is given in Table 3-94.

TAMS/Gradient

3.3.7 NOAA

Figure 3-10 illustrates how the database tables in the **NOAA** directory are linked. Table 3-95 and the table below list the database tables contained in the **NOAA** directory. Tables 3-96 through 3-102 comprise the data dictionaries for the above-mentioned tables. Glossary definitions can be found in the Phase 2 data glossaries. Groups for NOAA samples are the same as those for the Phase 2 ecological program and can be found in *PHASE2\ECO\GROUPS*.

Tables in NOAA Directory
(including Tables in *NOAA\QA_QC* subdirectory)

Table Name	Description
STATIONS	Ecological survey stations
COORDS	Coordinates for stations
FISH	Sample composition information - fish
PCBFISH	PCB congeners/homologue sum/Aroclor concentrations - fish
PCBFISHD	PCB congeners - fish dup pairs/dilution analyses
NONPCBB	Non-PCB data - biota
SPECIES	Key to species codes

The **STATIONS** table contains sample information such as **TAMS ID**, **TAMS Type** and **Species**, as well as station number and sample location by river mile. **COORDS** is linked to **STATIONS** through the **STATION** field and contains sampling locations by northing and easting pairs. The PCB data tables, **PCBFISH** and **PCBFISHD** (containing laboratory duplicate analyses for those samples requiring dilution), and **NONPCBB**, the non-PCB results table for fish (biota) samples are linked to the **STATIONS** table by **TAMS ID**, **TAMS Type** and **Species**. The tables **FISH** and **SPECIES** are similarly linked and contain field data and species information, respectively.

3.4 Database Application Examples

This section describes three example queries showing database manipulations of the draft Phase 2 data. While the examples are most relevant to the Phase 2 data tables, the same general concept may be applied to other subdirectories and data tables. Field definitions for all data tables are provided in the data dictionaries located in the Table Section of this report. The following discussion does not assume a specific database management software package, but rather relates general procedures for conducting database queries. The reader may need to refer to

software manuals for directions on performing queries for the specific database management software package being used.

1. *Extract Total PCB values and Total Carbon/Total Nitrogen Ratios from High-Resolution Sediment Coring Data for Correlation Analysis.*

This example demonstrates how to extract pairs of Total PCBs and Total Carbon/Total Nitrogen ratio from the high-resolution sediment core samples for the purpose of calculating correlation coefficients or performing other data analysis. The box below summarizes the steps and Figure 3-11 indicates the table links needed to accomplish the database query.

1. Move to the appropriate directory (*PHASE2\HRCORES*).
2. Select from **NONPCBS** all samples whose carbon to nitrogen ratio (C/N) is greater than 0.
3. Link through the **TAMS ID** and **TAMS Type** fields and select all the Total PCBs records from **PCBS**. (In this case, **Value2** has been selected to reflect the application of USEPA guidance regarding treatment of non-detected congener results.)
4. Save merged results to a table and export to a statistics program.

Example results are shown below (partial listing):

TAMS Sample ID	TAMS SampType	C/N - molar	Total PCBs - g/Kg DW*
HR-001-0002	P	13.60	534.35
HR-001-0204	P	12.60	950.00
HR-001-0406	P	12.50	902.37
HR-001-0608	P	13.30	1037.47
HR-001-0812	P	14.00	974.78
HR-001-1216	P	14.30	1191.13
HR-001-1620	P	15.80	1441.25
HR-001-2024	P	16.00	191.76
HR-001-2428	P	14.90	62.36
HR-001-2832	P	14.40	90.07
HR-001-3236	P	13.70	279.38
HR-001-3640	P	14.00	89.11
HR-001-4044	P	12.60	49.81

* The actual values may be different from those shown here.

The merged results can now be saved to a computer file for input to a statistics program for determining correlation coefficients.

2. *Extract Homologue Sums and Core Depth Intervals for High-Resolution Sediment Core Number 19 for Graphing a Depth Profile.*

This example query extracts homologue sums for sediment samples taken from core number 19 and pairs the results with core depth intervals for the purpose of generating a sediment profile. Figure 3-12 shows the table links.

1. Move to the appropriate directory (*PHASE2\HRCORES*).
2. Select from **STATIONS** all samples from station "HR-019" and link through the **TAMS ID** and **TAMS Type** fields to **PCBS**.
3. Input the criteria so as to exclude all congener records (those starting with "BZ") and include homologue sums only. (As above, **Value2** has been selected to reflect the application of USEPA guidance regarding treatment of non-detected congener results.)
4. Save merged results to a table and display.

Results displayed in a summary format are as follows:

Upper												Lower											
Depth	Depth	Mono*	Di*	Tri*	Tetra*	Penta*	Hexa*	Hepta*	Octa*	Nona*	Deca*												
(cm)	(cm)																						

0	2	2837.0	6652.9	8146.4	5284.7	2032.7	378.6	128.4	32.2	7.3	0.0												
2	4	4152.0	10410.4	10544.0	5070.9	1788.3	400.4	148.1	34.3	6.3	0.0	4	6	7731.0	16086.6	14792.0	6499.0	2145.7	434.9				
160.5	0.0	0.0	0.0																				
6	8	12160.0	27618.2	20753.5	8595.5	2680.0	632.6	222.7	38.3	8.5	0.0	8	12	43480.0	95862.0	48445.0	15893.0	3765.8	675.0				
196.9	0.0	0.0	0.0																				
8	16	115830.0	232219.0	92503.0	23288.7	7349.2	1343.0	286.0	0.0	0.0	0.0												
12	16	174150.0	238297.0	99322.7	29249.3	7986.8	823.0	0.0	0.0	0.0	0.0												
16	20	616800.0	845330.0	227040.8	75873.2	27533.4	4947.0	1589.0	0.0	0.0	0.0												
20	24	777750.0	1045244.0	263233.6	82505.9	26362.6	3441.0	1101.0	0.0	0.0	0.0												
24	28	185810.0	196751.0	61967.6	24304.9	7443.0	1781.0	165.0	0.0	0.0	0.0												
28	32	161340.0	261007.0	75486.4	23170.9	7101.2	3562.8	1423.6	557.9	222.0	0.0												
32	36	38080.0	53766.0	26134.6	8872.6	3607.0	1188.0	0.0	0.0	0.0	0.0												
36	40	2801.3	5483.9	1589.9	633.8	501.8	126.6	15.0	0.0	0.0	0.0												
40	44	7.9	12.6	39.5	18.4	6.4	1.9	.4	0.0	0.0	0.0	44	48	9.5	9.0	31.2	24.0	11.5	1.8				
0.0	48	52	5.4	7.2	14.6	9.3	4.8	.9	.7	0.0	0.0	0.0	52	56	8.0	7.4	17.9	13.0	7.4				
0.0	0.0	56	61	2.1	3.9	15.1	7.5	4.2	.7	.4	0.0	0.0	0.0										

* The actual values may be different from those shown here.

3. *Extract Five PCB Congeners from Water Samples Collected during Water Column*

TAMS/Gradient

Transect 2 and Link Them to Station River Mile.

Because of the quantity of information and sheer number of congeners, it may be more suitable to investigate a few at a time. Subsets of congeners are readily extracted from the database for purposes of data analyses. This example extracts five congeners from a single transect and associates the results with river mile. Refer to Figure 3-13.

1. Move to the appropriate directory (*PHASE2\WATER*).
2. Select from **STATIONS** all samples from transect 002 and link through the **TAMS ID** and **TAMS Type** fields to **PCBW**.
3. Indicate which congeners are to be included in the extracted subset: BZ#1, BZ#12, BZ#27, BZ#41, or BZ#84. (As above, **Value2** has been selected to reflect the application of USEPA guidance regarding treatment of non-detected congener results.)
4. Save merged results to a table and display.

Example results are given below:

Station	River Mile	BZ#1*	BZ#12*	BZ#27*	BZ#41*	BZ#84*
0001	201	0.00	0.00	0.00	0.00	.01
0002	197	0.00	0.00	0.00	0.00	0.00
0003	196	.17	.12	.10	.02	.02
0004	194	.24	.07	.15	.04	.02
0005	189	11.90	.03	1.32	.08	.07
0006	181	3.73	.02	.57	.10	.10
0007	168	3.51	.02	.55	.10	.07
0008	157	2.91	.02	.61	.08	.07

* The actual values may be different from those shown here.

PAGE INTENTIONALLY LEFT BLANK

4. REFERENCES

Armstrong, R. W. and R. J. Sloan. 1981. *PCB Patterns in Hudson River Fish. I. Resident/Freshwater Species*. NYSDEC, Albany, NY.

Bopp, R.F. 1979. *The Geochemistry of Polychlorinated Biphenyls in the Hudson River*. Columbia University, Ph.D. thesis.

Bopp, R.F., H.J. Simpson, C.R. Olsen, R.M. Trier and N. Kostyk, 1982. *Chlorinated Hydrocarbons and Radionuclide Chronologies in Sediments of the Hudson River and Estuary, New York*. Environmental Sci. Technol. 16(10):666 - 676.

Bopp, R.F. 1983. *Revised Parameters for Modeling the Transport of PCB Components Across an Air Water Interface*. Journal of Geophysical Research, 88(4).

Bopp, R. F., H. J. Simpson and B. L. Deck. 1985. *Release of Polychlorinated Biphenyls from Contaminated Hudson River Sediments*. Final Report to NYSDEC, Albany, NY; Contract No. NYS C00708.

Bopp, R.F. and H.J. Simpson. 1988. *Sources and Trends of Persistent Contaminants in New York Harbor Complex*. Final Report to Hudson River Foundation.

Bopp, R.F. and H.J. Simpson. 1989. *Contamination of the Hudson River. The Sediment Record in Contaminated Marine Sediments - Assessment and Remediation*, Committee on Contaminated Sediments, National Research Council, National Academy Press.

Brown, M.P., M.B. Werner, C.R. Carusone, and M. Klein. 1988. *Distribution of PCBs in the Thompson Island Pool of the Hudson River: Final Report of the Hudson River PCB Reclamation Demonstration Project Sediment Survey*. Division of Water, New York State Department of Environmental Conservation, Albany, NY.

Bush, B. and F. C. Lo. 1973. Thin-layer chromatography for quantitative polychlorinated biphenyl analysis. *J. Chromatogr.*, 77:377-388.

Claussen, J.H., General Electric Company. 1991. Letter to Douglas J. Tomchuk (USEPA Region II), dated March 8, 1991, regarding Hudson River PCBs Site, containing transmittal of GE 1990 sediment samples from selected locations.

Haggard, J.G., General Electric Company. 1994. Letter to Douglas J. Tomchuk (USEPA Region II), dated October 10, 1994, regarding Hudson River Remnant Deposits monthly progress report for September 1994.

Harza Engineering. 1990. *Ft. Edward Dam PCB Remnant Deposit Containment Environmental Monitoring Program Baseline Studies, Report of 1989 Results, August-December 1989*. Report

TAMS/Gradient

to General Electric Company, Fairfield, CT, February 1990.

Limburg, K.E. 1984. PCBs in the Hudson. In the *Hudson Review Ecosystem*. Springer-Verlag, NY, pp. 83-130.

Metcalf & Eddy. 1990. *Final Report, Waterford Drinking Water Supply Evaluation*. (Hudson River PCB Remnant Site Project - Task 3). Report prepared for NYSDEC, Albany, NY.

Novak, M.A., A.A. Reilly, and S.J. Jackling. 1988. Long-term monitoring of polychlorinated biphenyls in the Hudson River (New York) using caddisfly larvae and other macroinvertebrates. *Arch. Environ. Contam. Toxicol.* 17:699-711.

Novak, M.A., A.A. Reilly, B. Bush, and L. Shane. 1990. *In-situ* determination of PCB congener-specific first order absorption/desorption rate using *Chironomus tentans* larvae (Insecta: Diptera: Chironomidae). *Water Research* 24(3): 321-327.

NUS Corporation. 1984. *Feasibility Study: Hudson River PCBs Site, New York. Volume I*. Pittsburgh, PA.

NYS Thruway Authority, Office of Canals, 1993, Champlain Canal (Hudson River) Staff Gauge Readings between Lock 1 and Lock 7, Transmittals to TAMS Consultants from C. Head. Various dates.

O'Brien and Gere Engineers, Inc. 1993. Data Summary Reports, prepared for General Electric.

O'Brien and Gere Engineers, Inc. 1994. Fort Edward Dam PCB Remnant Containment 1993 Post Construction Monitoring Program, prepared for General Electric.

Rhea, J.R., O'Brien and Gere. 1994. Letter to Edward Garvey (TAMS Consultants, Inc.), dated March 15, 1994, regarding General Electric Co. Hudson River Project and transmittal of GE database.

Rhea, J.R., O'Brien and Gere. 1994a. Letter of transmittal from O'Brien and Gere to J. Haggard of GE, dated December 1, 1994, regarding updated General Electric Hudson River Database.

Rogers, Bob. 1991. Personal communication to Jonathan Butcher from Bob Rogers, USGS, Albany, NY.

Schroeder, R. A. and C. R. Barnes. 1983a. *Trends in Polychlorinated Biphenyl Concentrations in Hudson River Water Five Years after Elimination of Point Sources*. USGS Water-Resources Investigations Report 83-4206. USGS, Albany, NY.

Schroeder, R. A. and C. R. Barnes. 1983b. *Polychlorinated Biphenyl Concentrations in Hudson River Water and Treated Drinking Water at Waterford, New York*. USGS Water-Resources Investigations Report 83-4188. USGS, Albany, NY.

TAMS/Gradient

Simpson, K.W., M.A. Novak, and A.A. Reilly. 1986. *Final Report, Biomonitoring of PCBs in the Hudson River*. NYSDOH.

Sloan, R. 1994. Letter to D. Thomchuk - USEPA, A. DiBernardo - TAMS, and J. Haggard -GE, dated July 5, 1994, concerning transmittal of 1992 and 1993 NYSDEC Hudson River striped bass PCB data.

Sloan, R. J. and E.G. Horn. 1986. *Contaminants in Hudson River Striped Bass: 1978-1985*. Technical Report 86-2 (BEP), NYSDEC, Division of Fish and Wildlife, Albany, NY.

Sloan, R.J., B. Young, V. Vecchio, K. McKown, and E. O'Connell. 1988. *PCB Concentrations in the Striped Bass from the Marine District of New York State*. Technical Report 88-1 (BEP), Division of Fish and Wildlife, NYSDEC.

Spagnoli, J.J. and L.C. Skinner. 1977. PCBs in Fish from Selected Waters of New York State. *Pesticides Monitoring Journal*, 11(2):69-87.

TAMS Consultants, Inc. and Gradient Corp. 1992. *Phase 2A Sampling and Analysis Plan/Quality Assurance Project Plan Hudson River PCB Reassessment RI/FS*.

Tofflemire, T.J. and S.O. Quinn. 1979. *PCBs in the Upper Hudson River Mapping and Sediment Relationships*. NYSDEC, Technical Paper No. 56, Albany, NY. 140 pp.

Turk, J.T. and D. E. Troutman. 1981. *Polychlorinated Biphenyl Transport in the Hudson River, New York*. USGS Water-Resources Investigations Report 81-9. USGS, Albany, NY.

USEPA and NYSDEC. 1987. *Draft Joint Supplement to the Final Environmental Impact Statement on the Hudson River PCB Reclamation Demonstration Project and Appendices*.

USEPA. 1988. *Laboratory Data Validation Functional Guidelines for Evaluating Inorganics Analyses*.

USEPA. 1989. *Statistical Analysis of Ground-water Monitoring Data at RCRA Facilities - Interim Final Guidance*. EPA/530-SW-89-026. February.

USEPA. 1992. *Standard Operating Procedure (SOP) for the Evaluation of Metals Data for the Contract Laboratory Program (CLP) Inorganics Data Review for Region II (SOP No. HW-2, Rev. XI)*.

Wagner, L.A. 1980. *Drainage Areas of New York Streams by River Basin: A Stream Gazetteer*. USGS Water Resources Investigation, Open File.

Warren, S.D., R.F. Bopp and H.J. Simpson. 1987. *Volatilization of PCBs from Contaminated*

TAMS/Gradient

Sediments and Water. Final Report to NYSDEC, Albany, NY. Contract NYS COO1263.

WATSTORE, 1995. Retrieval from WATSTORE, USGS database, August 1995, by R. Allen of USGS-Water Division, Albany, NY.

Webb, R.G. and A.C. McCall. 1973. Quantitative PCB standards for electron capture gas chromatography. *J. Chromatographic Sci.*, 11: 366-73.

Weston Environmental Consultants. 1978. *Migration of PCBs from Landfills and Dredge Spoil Sites in the Hudson River Valley, New York -- Final Report*. Prepared for New York State Department of Environmental Conservation, Albany, NY.

Table 3-1
Data Dictionary for Table HIST_LUT in *HISTORIC* Directory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Fld_Param	[2]	A15	Contains all field name and parameters in <i>HISTORIC</i> Directory
Field Type	field_type	A3	[1]
Matrix	[2]	A30	Sample matrix
Units	[2]	A10	Units of result
Description	descriptio	A100	Definition of given field name or parameter
Database File	database_f	A50	Database files that contain given field or parameter
Memo	[2]	M	Additional information for certain fields/parameters

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[2] Same as Paradox

Table 3-2
Data Dictionary for Table PARAMKEY in *HISTORIC* Directory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Parameter code	parameter_0	A2	Parameter code
Parameter	parameter_1	A20	Name of parameter

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

Table 3-3
Tables in *HISTORIC\SED* Subdirectory

Table	Description
SAMPLES	Sediment sampling information; NYSDEC/OBG (1976 - 1978); NYSDEC/NYSDOH (1984 - 1985); GE/Harza (1990)
STATIONS	NYSDEC or GE station number correspondence to GradNo sample identifier
GRADNUMS	Core section correspondence to GradNo sample identifier
SECTION	Section number, depths, and correspondence to GradNo for sediment cores
REACHES	River reach numbers
CONCSED	PCB Aroclor data - sediment samples
NONCHEM	Non-PCB data - sediment samples
SOXHDUP	Duplicate PCB Aroclor data using soxhlet extraction
NONDETS	Key to non-detection qualifier codes
REF	Key to references used in building the database
TEXTURES	Sediment description key
GE89	Preliminary 1989 GE sediment baseline studies: GE/Harza (1989)
MASSPEC	Results for GMS performed for sediments collected during 1984-1985 NYSDEC survey of Upper Hudson

Table 3-4
Data Dictionary for Tables SAMPLES in *HISTORIC\SED* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
GradNo	gradientx	A5	Unique identifying number
Dup	dupx	A2	Duplicate marker field (not used)
Sample Type	sample_typ	A2	Sample Type (C = core, G = Grab)
Mo	month	A2	Sample month
Dy	day	A2	Sample day
Yr	year	A4	Sample year
Rmile	river_mile	N	Hudson River mile measured from the Battery
Distance ft	distancex	N	Distance from shore in feet
Northing ft	northingx	N	NY State Plane northing coordinate
Easting ft	easting_f	N	NY State Plane easting coordinate
Sampler	[2]	N	Sampling equipment
Water Depth ft	water_dept	N	Water depth in feet
Elevation ft	elevationx	N	Surface elevation in feet

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] Same as Paradox

Table 3-5
Data Dictionary for Table STATIONS in *HISTORIC\SED* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
GradNo	gradientx	A5	Unique identifying number
StationNo	stationx	A4	Station identifier for reference to NYSDEC or GE files

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

Table 3-6
Data Dictionary for Table GRADNUMS in *HISTORIC\SED* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
GradNo	gradientx	A5	Unique identifying number
SectionNo	sectionx	N	Core section number
IdentifierNo	identifier	A10	Identifier for reference to NYSDEC or GE files
Agency	[2]	A10	Agency collecting the data
Ref	refx	N	Reference number identifying source of data

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] Same as Paradox

Table 3-7
Data Dictionary for Table SECTION in *HISTORIC\SED* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
GradNo	gradientx	A5	Unique identifying number
SectionNo	sectionx	N	Core section number
Upper Depth inches	upper_dept	N	Top of core depth interval in inches
Lower Depth inches	lower_dept	N	Bottom of core depth interval in inches

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

Table 3-8
Data Dictionary for Table REACHES in *HISTORIC\SED* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Reach	[2]	N	Reach number
Lower Rmile	lower_rmil	N	Downstream endpoint river mile
Upper Rmile	upper_rmil	N	Upstream endpoint river mile

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] Same as Paradox

Table 3-9
Data Dictionary for Table CONCSED in *HISTORIC\SED* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
GradNo	gradientx	A5	Unique identifying number
Dups	[2]	A2	Duplicate marker field (not used)
SectionNo	sectionx	N	Core section number
Parameter	[2]	A20	Parameter name (Aroclor)
Extraction Method	extraction	A10	Extraction method code: shaker or soxhlet
Value	[2]	N	Positive numerical result
Det Limit	det_limit	N	Sample quantitation limit reported for non-detected result
Value and Limit Units	value_and	A3	Units of result or quantitation limit
Det?	detx	A3	Data qualifier (blank means detected; refer to NONDETS)

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] Same as Paradox

Table 3-10
Data Dictionary for Table NONCHEM in *HISTORIC\SED* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
GradNo	gradientx	A5	Unique identifying number
Dup	[2]	A2	Duplicate marker field
SectionNo	sectionx	N	Core section number
Parameter	[2]	A20	Parameter name (Aroclor)
Value	[2]	N	Numerical result

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] Same as Paradox

Table 3-11
Data Dictionary for Table SOXHDUP in *HISTORIC\SED* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
GradNo	gradientx	A5	Unique identifying number
SectionNo	sectionx	N	Core section number
Parameter	[2]	A20	Parameter name (Aroclor)
Extraction Method	extraction	A10	Extraction method code: shaker or soxhlet
Value	value_and	N	Positive numerical result
Det Limit	det_limit	N	Sample quantitation limit reported for non-detected result
Value and Limit Units	value_and	A3	Units of result or detection limit
Det?	detx	A3	Data qualifier (blank means detected; refer to NONDETS)

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] Same as Paradox

Table 3-12
Data Dictionary for Table NONDETS in *HISTORIC\SED* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Det Category	det_catag	A3	Non-detect code
Mass Spec Screen Categ	mass_specx	A6	Mass spectrometer (GMS) screening category
Mean Concentration, ppm	mean_conce	N	Mean concentration in the category in ppm
Value	[2]	N	Ranking of type of non-detect
Comment	[2]	A100	Comments

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] Same as Paradox

Table 3-13
Data Dictionary for Table REF in *HISTORIC\SED* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Ref	[2]	N	Reference number identifying data source
Description	descriptio	A40	Descriptor of data source

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[2] Same as Paradox

Table 3-14
Data Dictionary for Table TEXTURES in *HISTORIC\SED* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Texture#	texturex	N	Sediment texture code number
Texture	[2]	A7	Sediment texture code characters
Description	descriptio	A30	Sediment texture description

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] Same as Paradox

Table 3-15
Data Dictionary for Table GE89 in *HISTORIC\SED* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Gradient#	gradientx	A5	Unique identifying number
Identifier#	identifier	A4	Identifier for reference to NYSDEC or GE files
Agency	[2]	A10	Agency collecting the data
Ref#	refx	N6.0	Reference number identifying source of data
Location	[2]	A10	Location defined as per GE documentation
Sample Date	sample_dat	D	Sample date
Parameter	[2]	A2	Parameter key as defined in PARAMKEY and HIST-LUT
Det. Lim.-ppb	det__limxx	N	Sample quantitation limit reported for non-detected limit
Det.	detx	A3	ND=non-detect; blank=detect
Concentration-ppm	concentrat	N	Concentration in ppm

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] Same as Paradox

Table 3-16
Data Dictionary for Table MASSPEC in *HISTORIC\SED* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Gradient#	gradientx	A5	Unique identifying number
Dup	[2]	A2	Duplicate marker field (not used)
Section#	sectionx	N	Core section number
Mass Spec Screen Categ	mass_specx	A6	Mass spectrometer (GC/MS) screening category

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] Same as Paradox

Table 3-17
Tables in *HISTORIC\FISH* Subdirectory

Table Name	Description
GRADNUMF	Master index to GradNo
SAMPLEF	Fish sampling information
CORRNUM	Correspondence between old and new GradNo
COMPOS	Sample information for composite samples
CONCFISH	PCB Aroclor and percent lipid data - fish samples
PREP	Key to tissue and preparation codes
SPECCODE	Key to species codes
REF	Key to references used in building the database

Table 3-18
Data Dictionary for Table GRADNUMF in *HISTORIC\FISH* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
GradNo	[2]	A5	Unique identifying number
Labno	[2]	A11	Laboratory identifier for reference to the NYSDEC files
Tagno	[2]	A9	Tag identifier for reference to the NYSDEC files
Ref	[2]	A10	Reference number identifying data source
Comment	[2]	M25	Memo field recording alterations to the database and cross-reference on GradNo assignments

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] Same as Paradox

Table 3-19
Data Dictionary for Table SAMPLEF in *HISTORIC\FISH* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
GradNo	Gradientx	A5	Unique identifying number
Location	[2]	A50	Narrative record of location
Rmile	[2]	N	Hudson River mile measured from the Battery
Yr	[2]	N	Sample year
Mo	[2]	N	Sample month
Dy	[2]	N	Sample day
Spp	[2]	A5	Species code (refer to SPECCODE)
Basin	[2]	A8	Numeric designation of watershed basin
MnLen	[2]	N	Fish length in mm (for composites, this is the mean length)
MnWgt	[2]	N	Weight in grams (for composites, this is the mean weight)
Sex	[2]	A1	Fish gender (contains F, M, U, X, and blank)
Age	[2]	A1	Fish age (contains 0-8, F, I, O, U, Y, and * and not presently positively identified)
Prep	[2]	A3	Fish tissue and preparation codes (refer to PREP)
Noincomp	[2]	N	Number of fish in composites
UTMN	[2]	N	NY Transverse Mercator northing
UTME	[2]	N	NY Transverse Mercator easting
Verified	[2]	A2	NSYDEC verification status (T, F, blank) although meaning of code is not presently clear

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[2] Same as Paradox

Table 3-20
Data Dictionary for Table CORRNUM in *HISTORIC\FISH* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Oldno	[2]	A5	Old unique identifying number
Newno	[2]	A5	New unique identifying number

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[2] Same as Paradox

Table 3-21
Data Dictionary for Table COMPOS in *HISTORIC\FISH* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
GradNo	gradientx	A5	Unique identifying number
Noincomp	[2]	N	Number of individuals in composite
Mnlen	[2]	N	Mean length in composite
Minlen	[2]	N	Minimum length in composite
Maxlen	[2]	N	Maximum length in composite
Sdlen	[2]	N	Standard deviation of length
Mnwgt	[2]	N	Mean weight of individuals in composite (g)
Minwgt	[2]	N	Minimum weight in composite
Maxwgt	[2]	N	Maximum weight in composite
Sdwgt	[2]	N	Standard deviation of weight

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[2] Same as Paradox

Table 3-22
Data Dictionary for Table CONCFISH in *HISTORIC\FISH* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
GradNo	gradientx	A5	Unique identifying number
Parameter	[2]	A2	Parameter code (refer to PARAMKEY)
Value	[2]	N	Positive numeric result
Det Limit	det_or_qua	N	Sample detection limit reported for a non-detected result
Value and Limit Units	value_and	A3	Units of value or detection limit
Det or Qualifier	det_or_qu	A3	Data qualifier

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] Same as Paradox

Table 3-23
Data Dictionary for Table PREP in *HISTORIC\FISH* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Abbrev	[2]	A3	Tissue or preparation code
Tissue Type	tissue_typ	A30	Type of tissue in sample

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[2] Same as Paradox

Table 3-24
Data Dictionary for Table SPECCODE in *HISTORIC\FISH* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
SPP	[2]	A5	Species code
Species	[2]	A30	Name of species in sample

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[2] Same as Paradox

Table 3-25
Data Dictionary for Table REF in *HISTORIC\FISH* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Ref	[2]	N	Reference number identifying data source
Description	descriptio	A40	Descriptor of data source

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] Same as Paradox

Table 3-26
Tables in *HISTORIC\MACROINV* Subdirectory

Table Name	Description
SAMPLE	Macroinvertebrate sampling information
SAMPREF	Key to sample type
NUMINDI	Number of individuals in samples
CONC	PCB Aroclor results
OTHER	Additional species included in samples
SPECCODE	Species codes
DOHSITE	Multiple and caddisfly sampling information

Table 3-27
Data Dictionary for Table SAMPLE in *HISTORIC\MACROINV* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
GradNo	gradientx	A5	Unique identifying number
Location	[2]	A70	Location descriptor
Mo	[2]	A2	Sample month
Dy	[2]	A2	Sample day
Yr	[2]	N	Sample year
Rmile	[2]	N	River Mile measured from the Battery
Lab or EHC No	lab_or_ehc	A15	Laboratory identifier for reference to NYSDOH files
Tagno	[2]	A10	Tag identifier for reference to NYSDOH files
Species	[2]	N	Species code (refer to SPECCODE)
Sample type	sample_typ	A1	Sample type code (refer to SAMPREF)
Wet wt. (g)	wet_wt_gx	N	Sample wet weight in g
Dry wt. (g)	dry_wt_gx	N	Sample dry weight in g
Percent lipid	percent_li	N	Percent lipid content
PageNo	[2]	N	Reference page number

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] Same as Paradox

Table 3-28
Data Dictionary for Table SAMPREF in *HISTORIC\MACROINV* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Sample type	sample_typ	A1	Sample type code
Note	[2]	A80	Explanation

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] Same as Paradox

Table 3-29
Data Dictionary for Table NUMINDI in *HISTORIC\MACROINV* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
GradNo	gradientx	A5	Unique identifying number
Number of Individuals	number_of	N	Number of individuals in sample

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

Table 3-30
Data Dictionary for Table CONC in *HISTORIC\MACROINV* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
GradNo	gradientx	A5	Unique identifying number
Parameter	[2]	A20	Parameter name (Aroclor)
Value-ppm	value_ppm	N	Positive numerical result in ppm
Det Limit	det_limit	N	Sample quantitation limit reported for non-detected result
Det?	detx	A1	Denotes if sample is detected (y) or non-detected (n)

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[2] Same as Paradox

Table 3-31
Data Dictionary for Table OTHER in *HISTORIC\MACROINV* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
GradNo	[2]	A5	Unique identifying number
Other species	other_spec	N6.0	Other species number

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[2] Same as Paradox

Table 3-32
Data Dictionary for Table SPECCODE in *HISTORIC\MACROINV* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Species	[2]	N6.0	Species code
Species Name	species_na	A20	Name of species in sample

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[2] Same as Paradox

Table 3-33
Data Dictionary for Table DOHSITE in *HISTORIC\MACROINV* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Location	[2]	A8	Location descriptor code
Description	descriptio	A40	Description of the macroinvertebrate sampling site
Attachment	[2]	A20	Type of attachment
RMile	[2]	N	Hudson River mile measured from the Battery
Latitude	[2]	A10	Site latitude coordinate
Longitude	[2]	A10	Site longitude coordinate

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] Same as Paradox

Table 3-34
Data Dictionary for Table USGS_LUT in *USGS* Directory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Field Name	field_name	A30	Listing of all field names in <i>USGS</i> Directory
Field Type	field_type	A3	[1]
Description	descriptio	A100	Definition of given field name
Database File	database_x	A50	Database file(s) which contain given field name
Memo	[2]	M	Additional information for certain field names

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] Same as Paradox

Table 3-35
Tables in *USGS\FLOW* Subdirectory

Table Name	Description
FTEDWD	Mean daily Hudson River flow at Fort Edward, 1976-1993
GREEN	Mean daily Hudson River flow at Green Island, 1946-1993
HADLEY	Mean daily Hudson River flow at Hadley, 1921-1993
CORINTH	Mean daily Hudson River flow below Sacandaga River near Corinth, 1921-1993
SCHU	Mean daily Hudson River flow at Schuylerville, 1977-1979
STILL	Mean daily Hudson River flow at Stillwater, 1977-1979
WATR	Mean daily Hudson River flow at Waterford, 1976-1993
BATK	Mean daily Batten Kill flow at Battenville, 1922-1968
HOOS	Mean daily Hoosic River flow near Eagle Bridge, 1910-1993
SACAND	Mean daily Sacandaga River flow at Stewarts Bridge, 1907-1993
MOHK	Mean daily Mohawk River flow, 1917-1993
USGS7693	Mean daily flow at all above stations, except Battenville, 1976-1993

Table 3-36
Data Dictionary for All Tables in *USGS\FLOW* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Year	[2]	N	Measurement year
Month	[2]	N	Measurement month
Day	[2]	N	Measurement day
Flow_day	[2]	N	Sequential numbered day starting October 1 and ending September 30
Flow	[2]	N	Flow rate
Flow_units	[2]	A8	Flow rate units (cubic feet per second)
Station	[2]	A12	Station name

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] Same as Paradox

Table 3-37
Tables in *USGS\WQDATA* Subdirectory

Table Name	Description
USGSWQ	Water-column PCB, suspended sediment data, and sediment load, in tons/day, collected by the USGS
TOCDAT	Water-column total organic carbon (TOC) collected by the USGS

Table 3-38
Data Dictionary for Table USGSWQ in USGS\WQDATA Subdirectory
Page 1 of 2

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Station Name	station_na	A15	USGS Station Name
Sample Date	sample_dat	D	Sample date
Year	[2]	N	Sample year
Month	[2]	N	Sample month
Day	[2]	N	Sample day
Hour	[2]	N	Sample hour
Min	[2]	N	Sample minute
Inst. Discharge	inst_disc	N	Instantaneous discharge in units of cubic feet per second (cfs)
PCB Total	pcb_total	N	Total PCB value (ug/L)
PCB Dissolved	pcb_dissol	N	Dissolved PCB value (ug/L)
Suspended Sed	suspended	N	Total suspended sediment value (mg/L)
Key 2	key_2	N	1 indicates Total PCB value is below minimum detection limit
Key 3	key_3	N	1 indicates Dissolved PCB value is below minimum detection limit
Fines	[2]	N	Percent less than 0.062 mm
Sediment Load	sediment_l	N	Sediment load in tons/day
Aro1016	[2]	N	Aroclor 1016, in µg/L
Aro1016-ND	aro1016_nd	N	Aroclor 1016 - non-detect flag
Aro1221	[2]	N	Aroclor 1221, in µg/L
Aro1221-ND	aro1016_nd	N	Aroclor 1221 - non-detect flag
Aro1232	[2]	N	Aroclor 1232, in µg/L
Aro1232-ND	aro1232_nd	N	Aroclor 1232 - non-detect flag
Aro1242	[2]	N	Aroclor 1242, in µg/L
Aro1242-ND	aro1242_nd	N	Aroclor 1242 - non-detect flag
Aro1248	[2]	N	Aroclor 1248, in µg/L
Aro1248-ND	aro1248_nd	N	Aroclor 1248 - non-detect flag
Aro1254	[2]	N	Aroclor 1254, in µg/L

Table 3-38
Data Dictionary for Table USGSWQ in *USGS\WQDATA* Subdirectory
Page 2 of 2

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Aro1254-ND	aro1254_nd	N	Aroclor 1254 - non-detect flag
Aro1260	[2]	N	Aroclor 1260, in µg/L
Aro1260-ND	aro1260_nd	N	Aroclor 1260 - non-detect flag

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] Same as Paradox

Table 3-39
Data Dictionary for Table TOCDAT in *USGS\WQDATA* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Station Name	station_na	A15	USGS Station Name
Date	[2]	D	Sample date
TOC, mg/L	toc_mg_l	N	Total organic carbon (TOC) in mg/L

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] Same as Paradox

Table 3-40
Tables in *GE* Directory

Table Name	Description
SAMPLE	Sampling information for all GE data contained in this directory
PCB	Total PCBs data for all media
PCBHOMOL	PCB homologue data for all media
PCBCONG	PCB congener data for all media
NONPCB	Non-PCB data for all media
SPECCODE	Fish species code
PCB_LUT	Congener data glossary
GEPARAMS	Parameter abbreviations glossary
FIELD_LUT	Database field glossary

Table 3-41
Data Dictionary for Table SAMPLE in GE Directory
Page 1 of 2

Field Name [1] Paradox	Field Name FoxPro	Field Type [2]	Description [3]
NEA_file	[4]	C12	NEA file identification as reported on the PCB Congener Amount Report; "X" only means sample is a Temporal Water-Column Sample analyzed for dissolved PCBs
ID	[4]	A12	Unique identifier for environmental samples
Media	[4]	A1	Sample matrix: f=fish, w=water, a=air, b=biota, p=pore water, s=sediment, blank was assigned u=unknown
NEA_Desc	[4]	A40	NEA file description as reported on PCB summary report sheet
NEA_Com	[4]	A40	NEA comment as reported on PCB summary report sheet
Location	[4]	A10	Sample location
CP->Location	cp_locati	A25	Sample location from CP031194.DBF
CP->Mix_type	cp_mix_ty	A1	Type of mixed peak deconvolution as reported on the PCB congener amount report
Invest	[4]	A3	Organization that collected the sample
Lab	[4]	A8	Laboratory that performed the analysis
Customer	[4]	A20	Customer identification as reported on the PCB summary report sheet
Program	[4]	A20	Sampling program
Date_col	[4]	D	Sample date
St_dpth	[4]	N	Depth of top of sediment core (cm) or composite water sample (ft)
End_dpth	[4]	N	Depth of bottom of sediment core (cm) or composite water sample (ft)
Tot_diss	[4]	A1	Denotes total or dissolved (derived from a filtered water sample)
Desc	[4]	A150	Sample description
CP->Reach	cp_reach	A20	Hudson River reach where sediment samples were collected
CP->Sampsed	cp_sampse	A20	Sediment sample texture and ordinal descriptor

Table 3-41
Data Dictionary for Table SAMPLE in GE Directory
Page 2 of 2

Field Name [1] Paradox	Field Name FoxPro	Field Type [2]	Description [3]
Northing	[4]	N	1927 NY State Plane northing in ft (estimated for Temporal Water Column Sampling Program)
Easting	[4]	N	1927 NY state plane easting in ft (estimated for Temporal Water Column Sampling Program)
Elev	[4]	N	River elevation (estimated for Temporal Water Column Sampling Program)
Mile	[4]	N	River Mile designation (estimated at confluence for Batten Kill and Hoosic River Temporal Water Column Sampling locations; estimated for Float Survey sampling location; estimated at the midpoint of each of the sampling reaches for the Sediment Survey)
Hrcol	[4]	N	Sample hour
Mincol	[4]	N	Sample minute
GE->Verified	ge__verifi	A3	Verified data has been checked for accuracy and validated
OBG_ID	[4]	A8	O'Brien and Gere sample identification for parameters: TSS, TDS, SP_COND, TOT_ALK, TOC_F
Wtr_dpth	[4]	N	Water depth at sample location (ft)
Age	[4]	A1	Fish age in years
Len	[4]	N	Fish length in mm
Wgt	[4]	N	Fish weight in g
Sex	[4]	A1	Sex of fish: M=Male, F=Female, U=Undetermined
Spp	[4]	A4	Fish species (refer to SPECCODE)
Pclpd	[4]	N	Percent lipids
Prep	[4]	A3	Preparation method: F=Fillet, W=Whole fish, U=Unknown

[1] Fields overlapping between CP031194.DBF and GE031194.DBF are generally from GE031194.DBF unless specifically annotated with "CP->".

[2] A: character field with number denoting size of field

D: date field

N: number field

M: memo field

[3] Adapted from documentation provided by James R. Rhea, O'Brien & Gere Engineers (1994).

[4] Same as Paradox

Table 3-42
Data Dictionary for Table PCB in GE Directory

Field Name [1] Paradox	Field Name FoxPro	Field Type [2]	Description [3]
NEA_file	[4]	A12	NEA file identification as reported on the PCB Congener Amount Report; "X" only means sample is a Temporal Water Column Sample analyzed for dissolved PCBs
ID	[4]	A12	Unique sample identifier for environmental samples
Method	[4]	A20	Analysis method: Capillary Column, USGS, Webb & McCall
Col_type	[4]	A1	Column type: C=Capillary column, P=Packed column
Aroc_ID	[4]	A20	Visually identified nominal Aroclor pattern reported by NEA for Webb & McCall analyses
Parameter	[4]	A30	Parameter name
Value	[4]	N	Positive numerical result
DL_	dlx	N	Method detection limit reported for non-detected results
Units	[4]	A5	Units of result
Ql_	qlx	A2	Data validation qualifier: J=approximate sample result, U=approximate quantitation limit, UJ=approximate the sample result and the detection limit, R=reject the sample result or the detection limit

[1] Fields overlapping between CP031194.DBF and GE031194.DBF are generally from GE031194.DBF unless specifically annotated with "CP->".

[2] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[3] Adapted from documentation provided by James R. Rhea, O'Brien & Gere Engineers (1994).

[4] Same as Paradox

Table 3-43
Data Dictionary for Table PCBHOMOL in GE Directory

Field Name [1] Paradox	Field Name FoxPro	Field Type [2]	Description [3]
NEA_file	[4]	A7	NEA file identification as reported on the PCB Congener Amount Report, "X" only means sample is a Temporal Water Column Sample Analyzed for dissolved PCBs
ID	[4]	A12	Unique sample identifier for environmental samples
Parameter	[4]	A30	Parameter name
Value	[4]	N	Numerical result
Units	[4]	A20	Units of result

[1] Fields overlapping between CP031194.DBF and GE031194.DBF are generally from GE031194.DBF unless specifically annotated with "CP->".

[2] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[3] Adapted from documentation provided by James R. Rhea, O'Brien & Gere Engineers (1994).

[4] Same as Paradox

Table 3-44
Data Dictionary for Table PCBCONG in *GE* Directory

Field Name [1] Paradox	Field Name FoxPro	Field Type [2]	Description [3]
NEA_file	[4]	A7	NEA file identification as reported on the PCB Congener Amount Report, "X" only means sample is a Temporal Water Column Sample Analyzed for dissolved PCBs
ID	[4]	A12	Unique sample identifier for environmental samples
Parameter	[4]	A30	Parameter name
Value	[4]	N	Numerical result
Units	[4]	A20	Units of result

[1] Fields overlapping between CP031194.DBF and GE031194.DBF are generally from GE031194.DBF unless specifically annotated with "CP->".

[2] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[3] Adapted from documentation provided by James R. Rhea, O'Brien & Gere Engineers (1994).

[4] Same as Paradox

Table 3-45
Data Dictionary for Table NONPCB in *GE* Directory

Field Name [1] Paradox	Field Name FoxPro	Field Type [2]	Description [3]
NEA_file	[4]	A7	NEA file identification as reported on the PCB Congener Amount Report, "X" only means sample is a Temporal Water Column Sample Analyzed for dissolved PCBs
ID	[4]	A12	Unique sample identifier for environmental samples
Parameter	[4]	A30	Parameter name
Value	[4]	N	Numerical result
Units	[4]	A20	Units of result

[1] Fields overlapping between CP031194.DBF and GE031194.DBF are generally from GE031194.DBF unless specifically annotated with "CP->".

[2] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[3] Adapted from documentation provided by James R. Rhea, O'Brien & Gere Engineers (1994).

[4] Same as Paradox

Table 3-46
Data Dictionary for Table SPECCODE in *GE* Directory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Spp	[2]	A5	Species code
Species	[2]	A30	Name of species in samples

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] Same as Paradox

Table 3-47
Data Dictionary for Table PCB_LUT in GE Directory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Parameter	[2]	A11	Parameter code fr
NEA Parameter name	nea_parame	A31	Reported parameter name
Congener 1	congener_1	A45	First congener name or description
Congener 2	congener_2	A39	Second congener name if coelution
Congener 3	congener_3	A35	Third PCB congener name if coelution
Group	[2]	A7	Homologue group
BZ	[2]	A38	Corresponding BZ number

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] Same as Paradox

Table 3-48
Data Dictionary for Table GEPARAMS in *GE* Directory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Parameter	parameter_0	A20	Database parameter abbreviation
Parameter Name	parameter_1	A60	Parameter name

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

Table 3-49
Data Dictionary for Table FIELD_LUT in *GE* Directory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Field Name	field_name	A15	Contains all field names in GE Directory
Field Name	field_type	A3	[1]
Description	descriptio	A100	Definition of each field name
Database File	database_f	A30	Files that contain given field
Memo	[2]	M	Additional information on field names

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] Same as Paradox

Table 3-50
Data Dictionary for Table GAUGES in *NYSDOT* Directory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Year	[2]	N	Measurement year
Month	[2]	N	Measurement month
Day	[2]	N	Measurement day
Wy day	wy:day	N	Water year day
Gauge 119	gauge:119	N	Reading at staff gauge located below Lock 7 (Fort Edward) [3]
Gauge 118	gauge:118	N	Reading at staff gauge located above Crocker's Reef guard gate (Thompson Island Dam) at landcut portion of canal (near Fort Miller) [3]
Gauge 116	gauge:116	N	Reading at staff gauge located above Lock 6 (near Fort Miller) [3]
Gauge 115	gauge:115	N	Reading at staff gauge located below Lock 6 (near Fort Miller) [3]
Gauge 114	gauge:114	N	Reading at staff gauge located above Lock 5 (near Schuylerville) [3]
Gauge 113	gauge:113	N	Reading at staff gauge located below Lock 5 (near Schuylerville) [3]
Gauge 109	gauge:109	N	Reading at staff gauge located above Lock 4 (near Stillwater) [3]
Gauge 108	gauge:108	N	Reading at staff gauge located below Lock 4 (near Stillwater) [3]
Gauge 106	gauge:106	N	Reading at staff gauge located above Lock 3 (near Mechanicville) [3]
Gauge 105	gauge:105	N	Reading at staff gauge located below Lock 3 (near Mechanicville) [3]
Gauge 104	gauge:104	N	Reading at staff gauge located above Lock 2 (near Mechanicville) [3]
Gauge 103	gauge:103	N	Reading at staff gauge located below Lock 2 (near Mechanicville) [3]

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[2] Same as Paradox

[3] Reading in ft., relative to NYS Barge Canal Datum.
This reading can be converted to NGVD 1929 by subtracting 1.177 ft.

Table 3-51
Data Dictionary for Table CONG_LUT in *PHASE2* Directory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
BZ-No	bz_no	A3	Congener number
Parameter	[2]	A25	Contains all PCB parameters in <i>PHASE2</i> Directory
Homologue	[2]	A10	Classification based on number of chlorine atoms
Description	descript	A50	Definition of given PCB parameter
Conversion	[2]	A11	Correction factor see <i>PHASE2\FIELDS</i>
Target	[2]	A10	Yes: target congener (calibrated with standard) No: non-target congener No-cal: calibrated non-target congener Mix: congener pair coelutes
Unit_water	[2]	A8	Units for water samples, in ng/L
Unit_sed	[2]	A8	Units for sediment samples, in ug/Kg DW
Unit_part	[2]	A8	Units for particulate samples, in ug/kg DW
Subdirectory	Subdirectox	A45	<i>PHASE2</i> Subdirectory(ies) that contain given parameters
Database	[2]	A30	Database files that contain given parameter
Comment	[2]	A100	Comments

Table 3-52
Data Dictionary for Table FIELDS in *PHASE2* Directory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Field Name	field_name	A30	Contains database field names for <i>PHASE2</i> Directory
Field Type	field_type	A3	[1]
Description	descriptio	A100	Definition of field name
Database File	database_f	A100	Files that contain given field name
Memo	[2]	M	Additional information for certain fields

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] Same as Paradox

Table 3-53
Data Dictionary for Table PARAMS in *PHASE2* Directory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Parameter	[2]	A30	Contains every parameter in the <i>PHASE2</i> Directory
Matrix	[2]	A12	Sample matrix
Units	[2]	A15	Units of result
Description	descriptio	A100	Definition of given parameter
Subdirectory	[2]	A30	Lists <i>PHASE2</i> Subdirectories containing given parameter
Database	[2]	A30	Database table within subdirectories where given parameter can be found
Memo	[2]	M	Additional information for certain parameters

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] Same as Paradox

Table 3-54
Data Dictionary for Table QUALIFY in *PHASE2* Directory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
QA Comment	qa_comment	A5	Specific Quality Assurance qualifier [3]
Type	[2]	A30	Designates laboratory or data validation qualifier
Definition	[2]	M	Definition of QA Comment
Parameter Type	Parameter	A20	Parameter type for which qualifier is applicable
Assigned Qualifier	assigned_q	A5	Simplified reported qualification [3]

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[2] Same as Paradox

[3] QA Comment specifies the reason for qualification, e.g., why a value is estimated, while the Assigned Qualifier designates whether the value is non-detect estimated, presumed present, or rejected.

Table 3-55
Data Dictionary for Table AROCLSTD in PHASE2 Directory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Lab Sample ID	lab_sample	A10	Laboratory sample identifier
Sample ID	sample_id	A25	Sample identifier
Date Analyzed	date_analx	D	Data sample was analyzed
Matrix	[2]	A8	Sample matrix
Parameter	[2]	A28	Parameter name
Units	[2]	A10	Units of result
Value	[2]	N	Numerical result with non-detected values set to sample detection limit
Qualifier	[2]	A10	Data qualifier
Validated	[2]	A3	Field denoting if results have been validated (yes/no)

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] Same as Paradox

Table 3-56
Data Dictionary for Table ASCREEN in *PHASE2* Directory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Parameter	[2]	A28	Congener
1016	[2]	N	Aroclor 1016 [3]
1221	[2]	N	Aroclor 1221 [3]
1232	[2]	N	Aroclor 12321 [3]
1242	[2]	N	Aroclor 1242 [3]
1248	[2]	N	Aroclor 1248 [3]
1254	[2]	N	Aroclor 1254 [3]
1260	[2]	N	Aroclor 1260 [3]
1016-1242	1016_1242	N	Aroclors 1016 and 1242 [3]
1221-1232	1221_1232	N	Aroclors 1221 and 1232 [3]
1016-1248-1254	1016_1248x	N	Aroclors 1016, 1248 and 1254 [3]

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[2] Same as Paradox

[3] Congener is considered present in the Aroclor or sum of Aroclors when marked with a "1". Congener is absent when marked with a "0".

Table 3-57
Tables in *PHASE2\WATER* Subdirectory

Table Name	Description
STATIONS	Water column transects and flow-averaged events stations
GROUPS	Sample groupings
PCBP	PCB congeners/homologue sums/Aroclor concentrations - particulate samples (Fg/Kg)
PCBPD	PCB congeners - particulate duplicate pairs (Fg/Kg)
PCBPE	PCB congeners - particulate samples equilibration study (Fg/Kg)
PCBFA7	PCB congeners/homologue sums/Aroclor concentrations - combined particulate and dissolved samples (ng/L) for flow-averaged event 7
PCBW	PCB congeners/homologue sums/Aroclor concentrations - water samples (ng/L)
PCBWD	PCB congeners - water duplicate pairs (ng/L)
PCBWE	PCB congeners - water (dissolved) samples - equilibration study (ng/L)
PCBWTT	PCB congeners - whole water samples (TT series) (ng/L)
NONPCBW	Non-PCB data - water column samples
NONPCBWD	Non-PCB data - water duplicate sample pairs
FB	Non-PCB data - field blanks
VOLUMES	Sample volumes filtered for PCB analyses

Table 3-58
Data Dictionary for Table STATIONS in *PHASE2|WATER* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Transect	[2]	A5	Transect or flow-averaged sampling event number
Station	[2]	A6	Station number
TAMS ID	tams_id	A11	Sample identifier
TAMS Type	tams_type	A3	Sample type [3]
Date Sampled	date_sampl	D	Date sample was taken
Matrix	[2]	A6	Sample matrix (WATER, FILTER)
Est Easting	[2]	N	Estimated NY State Plane easting (ft)
Est Northing	[2]	N	Estimated NY State Plane northing (ft)
River Mile	river_mile	N	River mile measured from the Battery
Location	[2]	A30	Station description
Program	[2]	A3	Program abbreviation (TW, TS, TT, FW, TS) [4]
SAS No.	sas_nox	A18	Sample identifier for laboratory program
Comment	[2]	A120	Sample comment

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[2] Same as Paradox

[3] B: Field blank
C: Composite
D: Duplicate
M: Miscellaneous

[4] TS: Water column transect suspended matter sample
TT: Water column transect whole (total) water sample
TW: Water column transect filtered water sample
FS: Flow-average filtered water sample
FW: Flow-average suspended matter sample

Table 3-59
Data Dictionary for Table GROUPS in *PHASE2\WATER* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Station	[2]	A6	Station number
Group	[2]	A25	Group identifier

[1] A: character field with number denoting size of field
 D: date field
 N: number field

[2] Same as Paradox

Table 3-60
Data Dictionary for Tables PCBP, PCBW, PCBFA7, PCBPE, PCBWE
in *PHASE2*\WATER Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
TAMS ID	tams_id	A11	Sample identifier
TAMS Type	tams_type	A3	Sample type [2]
Split	[2]	A10	Field denoting if record represents a composite of duplicate analyses (Avg-FD - average of field duplicates); not contained in PCBFA7, PCBPE or PCBWE.
Matrix	[2]	A8	Sample matrix (WATER, FILTER)
Parameter	[2]	A28	Parameter name
Units	[2]	A10	Units of result
Value1	[2]	N	Numerical result with non-detected values set to sample detection limit [3]; in PCBFA7, value1=value
Value2	[2]	N	Numerical result with non-detected values set to 0 or 1/2 detection limit; not contained in PCBFA7
Qualifier	[2]	A5	Data qualifier
QA Comment	qa_comment	A10	Quality Assurance comment codes see <i>PHASE2</i> \QUALIFY
Validated?	validated	A3	Field denoting if results have been validated (Yes/No)

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[2] B: Field blank
C: Composite
D: Duplicate
M: Miscellaneous

[3] Homologue sums and Total PCBs values represent sums of detected values only.

Table 3-61
Data Dictionary for Tables PCBWTT, PCBWD, PCBPD
in *PHASE2\WATER* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
TAMS ID	tams_id	A11	Sample identifier
TAMS Type	tams_type	A3	Sample type [2]
Matrix	[3]	A8	Sample matrix (WATER, FILTER)
Parameter	[3]	A28	Parameter name
Units	[3]	A10	Units of result
Value	[3]	N	Numerical result with non-detected values set to sample detection limit
Qualifier	[3]	A5	Data qualifier
QA Comment	qa_comment	A10	Quality assurance comment codes see <i>PHASE2\QUALIFY</i>
Validated	[3]	A3	Field denoting if results have been validated (Yes/No)

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] B: Field blank
 C: Composite
 D: Duplicate
 M: Miscellaneous

[3] Same as Paradox

Table 3-62
Data Dictionary for Tables NONPCBW, NONPCBWD in *PHASE2\WATER* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
TAMS ID	tams_id	A11	Sample identifier
TAMS Type	tams_type	A3	Sample type [2]
SAS No.	sas_nox	A8	Sample identifier for laboratory program
Split	[3]	A10	Field denoting if record represents a composite of duplicate analyses (Avg-FD - average of field duplicates) in NONPCBW ; Non-blank entry in NONPCBWD represents a laboratory duplicate analysis
Laboratory	[3]	A10	Name of laboratory performing analysis
SDG No.	sdg_nox	A12	Sample delivery group (for data validation)
Parameter	[3]	A30	Parameter name
Units	[3]	A10	Units of result
Value	[3]	N	Numerical result with non-detected values set to sample detection limit
Qualifier	[3]	A4	Data qualifier
Validated	[3]	A4	Field denoting if results have been validated (Yes/No)

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] B: Field blank
 C: Composite
 D: Duplicate
 M: Miscellaneous

[3] Same as Paradox

Table 3-63
Data Dictionary for Table FB in PHASE2\WATER Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
TAMS ID	tams_id	A11	Sample identifier
TAMS Type	tams_type	A3	Sample type [2]
SAS No.	sas_nox	A8	Sample identifier for laboratory program
Split	[3]	A10	Non-blank entry denotes a laboratory duplicate or split sample
Laboratory	[3]	A10	Name of laboratory performing analysis
SDG No.	sdg_nox	A12	Sample delivery group (for data validation)
Parameter	[3]	A30	Parameter name
Units	[3]	A10	Units of result
Value	[3]	N	Numerical result with non-detected values set to sample detection limit
Qualifier	[3]	A4	Data qualifier

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[2] B: Field blank
C: Composite
D: Duplicate
M: Miscellaneous

[3] Same as Paradox

Table 3-64
Data Dictionary for Table VOLUMES in PHASE2\WATER Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
TAMSW	[2]	A11	Sample identifier - water sample
SampTypeW	[2]	A3	Sample type - water sample [3]
TAMSP	[2]	A11	Sample identifier - corresponding filtered sample
SampTypeP	[2]	A3	Sample type - corresponding filtered sample [3]
Volume Filtered	volume_fil	N	Volume filtered
Units	[2]	A4	Units of volume filtered

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] Same as Paradox

[3] B: Field blank
 C: Composite
 D: Duplicate
 M: Miscellaneous

Table 3-65
Tables in PHASE2\SEDIMENT Subdirectory

Table Name	Description
STATIONS	Confirmatory Sampling and High-Resolution Sediment Coring Program sampling stations
PCBS	PCB congeners/homologue sums/Aroclor sums - sediment samples ($\mu\text{g/kg DW}$)
PCBSD	PCB congeners - duplicate sediment sample pairs ($\mu\text{g/kg DW}$)
NONPCBS	Non-PCB data - sediment samples
NONPCBSD	Non-PCB data - duplicate sediment sample pairs
FB	Non-PCB data - field blanks
SIEVEGS	ASTM Grain size distribution data by sieve analysis
SIEVEGSD	ASTM Grain size distribution data by sieve analysis - sample duplicates
LASERGS	Grain size distribution data by laser particle analysis
LASERGSD	Grain size distribution data by laser particle analysis - sample duplicates
RADNUC	Radionuclide data - sediment samples
RADNUCD	Radionuclide data - sediment samples field duplicates
LRINFO	Supplemental Low Resolution Sediment Coring Program information
SEDDESC	Descriptive sediment classifications density, redox and other field data

Table 3-66
Data Dictionary for Table STATIONS in *PHASE2\SEDIMENT* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Station	[2]	A8	Station number
TAMS ID	tams_id	A11	Sample identifier
TAMS Type	tams_type	A3	Sample type [3]
Date Sampled	date_sampl	D	Date sample was taken
Time Sampled	time_sampl	A10	Time sample was taken
Lower Depth (cm)	lower_dept	N	Depth of top of sediment slice (cm)
Upper Depth (cm)	upper_dept	N	Depth of bottom of sediment slice (cm)
Easting	[2]	N	NY State Plane easting (ft)
Northing	[2]	N	NY State Plane northing (ft)
Location	[2]	A30	Station description
Program	[2]	A3	Program abbreviation (HR, CS, CG) [4]
SAS No.	sas_nox	A10	Sample identifier for laboratory program
Comment	[2]	A120	Sample comment

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[2] Same as Paradox

[3] A: Archive core
B: Field blank
D: Duplicate core
G: Grain-size core
M: Matrix spike sample or core
P: PCB core
X: X-Ray core

[4] CC: Confirmatory sampling core
CG: Confirmatory sampling grab
HR: High-resolution sediment core
LR: Low-resolution sediment core

Table 3-67
Data Dictionary for Table PCBS in PHASE2\SEDIMENT Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
TAMS ID	tams_id	A11	Sample identifier
TAMS Type	tams_type	A3	Sample type [2]
Split	[3]	A10	Field denoting if record represents a composite of duplicate analyses (Avg-FD - average of field duplicates)
Matrix	[3]	A8	Sample matrix (SED)
Parameter	[3]	A28	Parameter name
Units	[3]	A10	Units of result
Value1	[3]	N	Numerical result with non-detected values set to sample quantitation limit [4]
Value2	[3]	N	Numerical result with non-detected values set to 0 of 1/2 quantitation limit
Qualifier	[3]	A5	Data qualifier
QA Comment	qa_comment	A10	Quality Assurance comment code see PHASE2\QUALIFY
Validated?	validated	A3	Field denoting if results have been validated (Yes/No)

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[2] A: Archive core
B: Field blank
D: Duplicate core
G: Grain-size core
M: Matrix spike sample or core
P: PCB core
X: X-Ray core

[3] Same as Paradox

[4] Homologue sums and Total PCBs values represent sums of detected values only.

Table 3-68
Data Dictionary for Tables PCBSD in PHASE2\SEDIMENT Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
TAMS ID	tams_id	A11	Sample identifier
TAMS Type	tams_type	A3	Sample type [2]
Matrix	[3]	A8	Sample matrix (SED)
Parameter	[3]	A28	Parameter name
Units	[3]	A10	Units of result
Value	[3]	N	Numerical result with non-detected values set to sample detection limit
Qualifier	[3]	A5	Data qualifier
QA Comment	qa_comment	A10	Quality Assurance comment code see <i>PHASE2\QUALIFY</i>
Validated	[3]	A3	Field denoting if results have been validated (Yes/No)
Date Sampled	date_sampl	D	Date sample was taken

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[2] A: Archive core
B: Field blank
D: Duplicate core
G: Grain-size core
M: Matrix spike sample or core
P: PCB core
X: X-Ray core

[3] Same as Paradox

Table 3-69
Data Dictionary for Tables NONPCBS, NONPCBSD, SIEVEGS, SIEVEGSD, LASERGS,
LASERGSD in PHASE2\SEDIMENT Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
TAMS ID	tams_id	A11	Sample identifier
TAMS Type	tams_type	A3	Sample type [2]
SAS No.	sas_nox	A8	Sample identifier for laboratory program
Split	[3]	A10	Field denoting if record represents a composite of duplicate analyses (Avg-FD - average of field duplicates) in NONPCBS ; Non-blank entry in NONPCBSD represents a laboratory duplicate analysis
Laboratory	[3]	A10	Name of laboratory performing analysis
SDG No.	sdg_nox	A12	Sample delivery group (for data validation)
Parameter	[3]	A30	Parameter name
Units	[3]	A10	Units of result
Value	[3]	N	Numerical result with non-detected values set to sample detection limit
Qualifier	[3]	A4	Data qualifier
Validated	[3]	A4	Field denoting if results have been validated (Yes/No)

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[2] A: Archive core
B: Field blank
D: Duplicate core
G: Grain-size core
M: Matrix spike sample or core
P: PCB core
X: X-Ray core

[3] Same as Paradox

Table 3-70
Data Dictionary for Table FB in PHASE2\SEDIMENT Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
TAMS ID	tams_id	A11	Sample identifier
TAMS Type	tams_type	A3	Sample type [2]
SAS No.	sas_nox	A8	Sample identifier for laboratory program
Split	[3]	A10	Non-blank entry denotes a laboratory duplicate or split sample
Laboratory	[3]	A10	Name of laboratory performing analysis
SDG No.	sdg_nox	A12	Sample delivery group (for data validation)
Parameter	[3]	A30	Parameter name
Units	[3]	A10	
Value	[3]	N	Numerical result with non-detected values set to sample detection limit
Qualifier	[3]	A3	Data qualifier

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[2] A: Archive core
B: Field blank
D: Duplicate core
G: Grain-size core
M: Matrix spike sample or core
P: PCB core
X: X-Ray core

[3] Same as Paradox

Table 3-71
Data Dictionary for Tables RADNUC, RADNUCD in PHASE2\SEDIMENT Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
TAMS ID	tams_id	A11	Sample identifier
TAMS Type	tams_type	A3	Sample type [2]
Split	[3]	A4	Non-blank entry denotes a laboratory duplicate or split sample
Laboratory	[3]	A10	Name of laboratory performing analysis
SDG No.	sdg_nox	A5	Sample delivery group (for data validation)
Date Sampled	date_sampl	D	Date sample was taken
Counting Date	counting_d	D	Date sample was counted
Detector	[3]	A11	Detector type
Parameter	[3]	A30	Parameter name
Units	[3]	A10	Units of result
Sigma	[3]	N	Standard deviation associated with counting result
Value	[3]	N	Numerical result with non-detected values set to sample quantitation limit
Det Limit	det_limit	N	Reported counter detector limit
Qualifier	[3]	A3	Data qualifier
Validated	[3]	A4	Field denoting if results have been validated (Yes/No)

[1] A: character field with number denoting size of field
D: date field
N: number field

[2] Sample Type Categories
A: Archive core
B: Field blank
D: Duplicate core
G: Grain-size core
M: Matrix spike sample or core
P: PCB core
X: X-Ray core

[3] Same as Paradox

Table 3-72
Data Dictionary for Table LRINFO in *PHASE2\SEDIMENT* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
TAMS ID	tams_id	A11	Sample identifier
TAMS Type	tams_type	A3	Sample type [2]
NYSDEC No.	nysdec_nox	A8	Corresponding 1984 NYSDEC Sediment Survey Station No. (from Brown et. al 1988)
Hotspot No.	hotspot_nx	A10	NYSDEC Hotspot Number

[1] A: character field with number denoting size of field
D: date field
N: number field

[2] Sample Type Categories
A: Archive core
B: Field blank
D: Duplicate core
G: Grain-size core
M: Matrix spike sample or core
P: PCB core
X: X-Ray core

Table 3-73
Data Dictionary for Table SEDDESC in PHASE2\SEDIMENT Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
TAMS ID	tams_id	A11	Sample identifier
TAMS Type	tams_type	A3	Sample type [2]
Eh	[3]	N	Redox potential in meV
Temperature	temperatur	N	Temperature of redox measurement in EC
Field Comment	field_comm	A50	Comments from field notes
Color_1	[3]	A5	Primary sediment coloration noted in field
Color_2	[3]	A5	Secondary sediment coloration noted in field
Sed_Clas_1	[3]	A5	TAMS descriptive sediment classification (based on ASTM method)
Sed_Clas_2	[3]	A5	TAMS descriptive sediment classification (based on ASTM method)
Sed_Clas_3	[3]	A5	TAMS descriptive sediment classification (based on ASTM method)
Sed_Clas_4	[3]	A5	TAMS descriptive sediment classification (based on ASTM method)
Sed_Clas_5	[3]	A7	TAMS descriptive sediment classification (based on ASTM method)
Description	descriptio	A120	Complete field description of sediment characteristics
Wet Weight	wet_weight	N	Wet weight of sample, in grams
Volume	[3]	N	Volume of container, in cc
Bulk Density	bulk_densi	N	Bulk density of sample, in g/cc
Percent Solids	percent_so	N	Measured percent of solids
Particle Density	particle_x	N	Particle density, in g/cc

[1] A: character field with number denoting size of field
D: date field
N: number field

[2] Sample Type Categories
A: Archive core
B: Field blank
D: Duplicate core
G: Grain-size core
M: Matrix spike sample or core
P: PCB core
X: X-Ray core

[3] Same as Paradox

TAMS/Gradient

Table 3-74
Tables in PHASE2\ECO Subdirectory

Table Name	Description
STATIONS	Ecological survey stations
COORDS	Coordinates for stations
GROUPS	Sample groupings
BENTHIC	Sample composition information - invertebrates
FISH	Sample composition information - fish
PCBFISH	PCB congeners/homologue sum/Aroclor concentrations - fish
PCBFISHD	PCB congeners - fish dup pairs/dilution analyses
PCBINV	PCB congeners/homologue sum/Aroclor concentrations - invertebrates
PCBINVD	PCB congeners - invertebrate dup. pairs/dilution analyses
NONPCBB	Non-PCB data - biota
NONPCBBD	Non-PCB data - biota duplicate pairs
PCBS	PCB congeners/homologue sums/Aroclor concentrations - sediment samples (ug/kg DW)
PCBSD	PCB congeners - sediment duplicate pairs (ug/kg DW))
NONPCBS	Non-PCB data - sediment samples
NONPCBSD	Non-PCB data - sediment duplicate pairs
LASERGS	Sediment laser grain size data
FB	Non-PCB data - sediment field blanks
SPECIES	Key to species codes
LASERGSD	Sediment laser grain size data - duplicate pairs

Table 3-75
Data Dictionary for Table STATIONS in *PHASE2\ECO* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Station	[2]	A8	Station number
TAMS ID	tams_id	A11	Sample identifier
TAMS Type	tams_type	A3	Sample type [3]
Species	[2]	A4	Species code
Date Sampled	date_sampl	D	Date sample was taken
Est Easting	est_eastin	N	Estimated NY State Plane easting (ft)
Est Northing	est_northi	N	Estimated NY State Plane northing (ft)
River Mile	river_mile	N	Mile measured from the Battery
Description	descriptio	A26	Station description
Program	[2]	A3	Program abbreviation (EC) [4]
SAS No.	sas_nox	A8	Sample identifier for laboratory program
RAS No.	ras_nox	A8	Second sample identifier for laboratory program
Comment.	[2]	A120	Sample comment

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] Same as Paradox

[3] B: Field blank
 D: Duplicate sample

[4] EC: Ecological survey

Table 3-76
Data Dictionary for Table COORDS in *PHASE2\ECO* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Station	[2]	A16	Station name
Est Easting	[2] est_eastin	N	Estimated NY State Plane easting (ft)
Est Northing	[2] est_northin	N	Estimated NY State Plane northing (ft)
Sample Type	sample_typ	A23	Type of sample taken
Fish Type	fish_typ	A18	Type of fish taken

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] Same as Paradox

Table 3-77
Data Dictionary for Table GROUPS in *PHASE2\ECO* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Station	[2]	A8	Station number
Group	[2]	A25	Group identifier

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] Same as Paradox

Table 3-78
Data Dictionary for Table BENTHIC in *PHASE2/ECO* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
TAMS ID	tams_id	A11	Sample identifier
TAMS Type	tams_type	A3	Sample type [2]
Species	[3]	A8	Species code
SAS No.	sas_nox	A8	Laboratory identifier
Wet Weight (mg)	wet_weight	N	Sample wet weight in mg
Comments	[3]	A160	Sample comment

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] B: Field blank
 D: Duplicate sample

Table 3-79
Data Dictionary for Table FISH in *PHASE2/ECO* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
TAMS ID	tams_id	A11	Sample identifier
TAMS Type	tams_type	A3	Sample type [2]
Species	[3]	A8	Species code
SAS No.	sas_nox	A8	Laboratory identifier
# of fish in sample	xxof_fish	N	Number of fish in samples
L1 (mm)	l1_mmx	N	Length in mm of fish number 1
L2 (mm)	l2_mmx	N	Length in mm of fish number 2
L3 (mm)	l3_mmx	N	Length in mm of fish number 3
L4 (mm)	l4_mmx	N	Length in mm of fish number 4
L5 (mm)	l5_mmx	N	Length in mm of fish number 5
L6 (mm)	l6_mmx	N	Length in mm of fish number 6
L7 (mm)	l7_mmx	N	Length in mm of fish number 7
L8 (mm)	l8_mmx	N	Length in mm of fish number 8
Length#	lengthx	N	Number of fish used to determine average length
Sum	[3]	N	Sum of fish lengths used to determine average lenth
Average length	average_le	N	Average of lengths
Average weight	average_we	N	Average of weights
Bulk weight	bulk_weigh	N	Total weight of the fish sample

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[2] B: Field blank
D: Duplicate sample

[3] Same as Paradox

Table 3-80
Data Dictionary for Tables PCBS, PCBINV, PCBFISH in *PHASE2\ECO* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
TAMS ID	tams_id	A11	Sample identifier
TAMS Type	tams_type	A3	Sample type [2]
Species	[3]	A4	Species code (not present in PCBS)
Split	[3]	A10	Field denoting if record represents a composite of duplicate analyses (Avg-FD - average of field duplicates)
Matrix	[3]	A10	Sample matrix (SED, BIOTA)
Parameter	[3]	A28	Parameter name
Units	[3]	A10	Units of result
Value1	[3]	N	Numerical result with non-detected values set to sample quantitation limit [4]
Value2	[3]	N	Numerical result with non-detected values set to 0 of 1/2 quantitation limit
Qualifier	[3]	A6	Data qualifier
QA Comment	qa_comment	A10	Quality Assurance comment code see <i>PHASE2\QUALIFY</i>
Validated?	validated	A3	Field denoting if results have been validated (Yes/No)

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[2] B: Field blank
D: Duplicate sample

[3] Same as Paradox

[4] Homologue sums and Total PCBs values represent sums of detected values only.

Table 3-81
Data Dictionary for Tables PCBSD, PCBINVD, PCBFISHD in *PHASE2\ECO* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
TAMS ID	tams_id	A11	Sample identifier
TAMS Type	tams_type	A3	Sample type [2]
Matrix	[3]	A8-A10	Sample matrix (SED, BIOTA)
Parameter	[3]	A28	Parameter name
Units	[3]	A10	Units of result
Species	[3]	A4	Contained in PCBINVD only
Value	[3]	N	Numerical result with non-detected values set to sample quantitation limit; PCBINVD contains value1 and value2
Qualifier	[3]	A6-A10	Data qualifier
QA Comment	qa_comment	A10	Quality Assurance comment code see <i>PHASE2\QUALIFY</i>
Validated	[3]	A3	Field denoting if results have been validated (Yes/No)

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] B: Field blank
 D: Duplicate sample

[3] Same as Paradox

Table 3-82
Data Dictionary for Tables NONPCBB, NONPCBBD, NONPCBS, NONPCBSD, LASERGS,
LASERGSD in PHASE2\ECO Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
TAMS ID	tams_id	A11	Sample identifier
TAMS Type	tams_type	A3	Sample type [2]
Species	[3]	A4	Species code (not present in NONPCBS , NONPCBSD or LASERGS)
SAS No.	sas_nox	A8	Sample identifier for laboratory program
Split	[3]	A10	Field denoting if record represents a composite of duplicate analyses (Avg-FD - average of field duplicates) in NONPCBB or NONPCBS ; non- blank entry in NONPCBBD or NONPCBSD represents a laboratory duplicate analysis
Laboratory	[3]	A10	Name of laboratory performing analysis
SDG No.	sdg_nox	A12	Sample delivery group (for data validation)
Parameter	[3]	A30	Parameter name
Units	[3]	A10	Units of result
Value	[3]	N	Numerical result with non-detected values set to sample detection limit
Qualifier	[3]	A4	Data qualifier
Validated	[3]	A4	Field denoting if results have been validated (Yes/No)

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[2] B: Field blank
D: Duplicate sample

[3] Same as Paradox

Table 3-83
Data Dictionary for Table FB in *PHASE2/ECO* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
TAMS ID	tams_id	A11	Sample identifier
TAMS Type	tams_type	A3	Sample type [2]
SAS No.	sas_nox	A8	Sample identifier for laboratory program
Split	[3]	A10	Non-blank entry denotes a laboratory duplicate or split sample
Laboratory	[3]	A10	Name of laboratory performing analysis
SDG No.	sdg_nox	A12	Sample delivery group (for data validation)
Parameter	[3]	A30	Parameter name
Value	[3]	N	Numerical result with non-detected values set to sample detection limit
Qualifier	[3]	A4	Data qualifier

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] B: Field blank
 D: Duplicate core

[3] Same as Paradox

Table 3-84
Data Dictionary for Table SPECIES in *PHASE2\ECO* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type	Description
Species	[2]	A8	Species code
Definition	[2]	A20	Definition of species code

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[2] Same as Paradox

TABLE 3-85
Tables in *PHASE2\HRCORES* Subdirectory

Table Name	Description
STATIONS	Confirmatory Sampling and High-Resolution Sediment Coring Program sampling stations
PCBS	PCB congeners/homologue sums/Aroclor sums - sediment samples (µg/kg DW)
PCBSD	PCB congeners - duplicate sediment sample pairs (µg/kg DW)
NONPCBS	Non-PCB data - sediment samples
NONPCBSD	Non-PCB data - duplicate sediment sample pairs
FB	Non-PCB data - field blanks
LASERGS	Laser grain size Phi classes
LASERGSD	Laser grain size Phi classes - duplicate pairs
RADNUC	Radionuclide data - sediment samples
RADNUCD	Radionuclide data - sediment samples field duplicates
SEDDESC	Redox, density and additional field information
GROUPS	Sample groupings

TABLE 3-86
Data Dictionary for Table STATIONS in *PHASE2\HRCORES* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Station	[2]	A8	Station number
TAMS ID	tams_id	A11	Sample identifier
TAMS SampType	tams_type	A3	Sample type [3]
Date Sampled	date_sampl	D	Date sample was taken
Time Sampled	time_sampl	A10	Time sample was taken
Lower Depth (cm)	lower_dept	N	Depth of top of sediment slice (cm)
Upper Depth (cm)	upper_dept	N	Depth of bottom of sediment slice (cm)
River Mile	river_mile	N	River mile measured from the Battery
Est Easting	[2]	N	Estimated NY State Plane easting (ft)
Est Northing	[2]	N	Estimated NY State Plane northing (ft)
Location	[2]	A30	Station description
Program	[2]	A3	Program abbreviation (HR, CS, CG) [4]
SAS No.	sas_nox	A10	Sample identifier for laboratory program
Comment	[2]	A120	Sample comment

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[2] Same as Paradox

[3] A: Archive core
B: Field blank
D: Duplicate core
G: Grain size core
M: Matrix spike sample or core
P: PCB core
X: X-Ray core

[4] CC: Confirmatory sampling core
CG: Confirmatory sampling grab
HR: High-resolution sediment core
LR: Low-resolution sediment core

TABLE 3-87
Data Dictionary for Table GROUPS in *PHASE2\HRCORES* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Station	[2]	A8	Station number
Group	[2]	A25	Group identifier

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] Same as Paradox

TABLE 3-88
Data Dictionary for Table PCBS in *PHASE2\HRCORES* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
TAMS ID	tams_id	A11	Sample identifier
TAMS Type	tams_type	A3	Sample type [2]
Split	[3]	A10	Field denoting if record represents a composite of duplicate analyses (Avg-FD - average of field duplicates)
Matrix	[3]	A8	Sample matrix (SED)
Parameter	[3]	A28	Parameter name
Units	[3]	A10	Units of result
Value1	[3]	N	Numerical result with non-detected values set to sample quantitation limit [4]
Value2	[3]	N	Numerical result with non-detected values set to 0 of 1/2 quantitation limit
Qualifier	[3]	A5	Data qualifier
QA Comment	qa_comment	A10	Quality Assurance comment code see <i>PHASE2\QUALIFY</i>
Validated?	validated	A3	Field denoting if results have been validated (Yes/No)

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[2] A: Archive core
B: Field blank
D: Duplicate core
G: Grain size core
M: Matrix spike sample or core
P: PCB core
X: X-Ray core

[3] Same as Paradox

[4] Homologue sums and Total PCBs values represent sums of detected values only.

Table 3-89
Data Dictionary for Tables PCBSD in PHASE2\HRCORES Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
TAMS Sample ID	tams_sampl	A11	Sample identifier
TAMS SampType	tams_sampt	A3	Sample type [2]
Matrix	[3]	A8	Sample matrix (SED)
Parameter	[3]	A28	Parameter name
Units	[3]	A10	Units of result
Value	[3]	N	Numerical result with non-detected values set to sample detection limit
Qualifier	[3]	A5	Data qualifier
Validated	[3]	A3	Field denoting if results have been validated (Yes/No)
Date Sampled	date_sampl	D	Date sample was taken

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] A: Archive core
 B: Field blank
 D: Duplicate core
 G: Grain size core
 M: Matrix spike sample or core
 P: PCB core
 X: X-Ray core

[3] Same as Paradox

Table 3-90
Data Dictionary for Tables NONPCBS, NONPCBSD, LASERGS, LASERGS in
PHASE2/HRCORES Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
TAMS ID	tams_id	A11	Sample identifier
TAMS Type	tams_type	A3	Sample type [2]
SAS No.	sas_nox	A8	Sample identifier for laboratory program
Split	[3]	A10	Field denoting if record represents a composite of duplicate analyses (Avg-FD - average of field duplicates) in NONPCBS ; non-blank entry in NONPCBSD represents a laboratory duplicate analysis
Laboratory	[3]	A10	Name of laboratory performing analysis
SDG No.	sdg_nox	A12	Sample delivery group (for data validation)
Parameter	[3]	A30	Parameter name
Units	[3]	A10	Units of result
Value	[3]	N	Numerical result with non-detected values set to sample detection limit
Qualifier	[3]	A4	Data qualifier
Validated	[3]	A4	Field denoting if results have been validated (Yes/No)

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[2] A: Archive core
B: Field blank
D: Duplicate core
G: Grain size core
M: Matrix spike sample or core
P: PCB core
X: X-Ray core

[3] Same as Paradox

Table 3-91
Data Dictionary for Table FB in PHASE2\HRCORES Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
TAMS ID	tams_id	A11	Sample identifier
TAMS Type	tams_type	A3	Sample type [2]
SAS No.	sas_nox	A8	Sample identifier for laboratory program
Split	[3]	A10	Non-blank entry denotes a laboratory duplicate or split sample
Laboratory	[3]	A10	Name of laboratory performing analysis
SDG No.	sdg_nox	A12	Sample delivery group (for data validation)
Parameter	[3]	A30	Parameter name
Units	[3]	A10	Units of result
Value	[3]	N	Numerical result with non-detected values set to sample detection limit
Qualifier	[3]	A3	Data qualifier

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[2] A: Archive core
B: Field blank
D: Duplicate core
G: Grain size core
M: Matrix spike sample or core
P: PCB core
X: X-Ray core

[3] Same as Paradox

Table 3-92
Data Dictionary for Tables RADNUC, RADNUCD in PHASE2\HRCORES Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
TAMS ID	tams_id	A11	Sample identifier
TAMS Type	tams_type	A3	Sample type [2]
Split	[3]	A4	Non-blank entry denotes a laboratory duplicate or split sample
Laboratory	[3]	A10	Name of laboratory performing analysis
SDG No.	sdg_nox	A5	Sample delivery group (for data validation)
Date Sampled	date_sampl	D	Sample date
Counting Date	counting_d	D	Date sample was counted
Detector	[3]	A11	Detector type
Parameter	[3]	A30	Parameter name
Units	[3]	A10	Units of result
Sigma	[3]	N	Standard deviation associated with counting result
Value	[3]	N	Numerical result with non-detected values set to sample quantitation limit
Det Limit	det_limit	N	Reported counter detector limit
Qualifier	[3]	A3	Data qualifier
Validated	[3]	A4	Field denoting if results have been validated (Yes/No)

[1] A: character field with number denoting size of field
D: date field
N: number field

[2] Sample Type Categories
A: Archive core
B: Field blank
D: Duplicate core
G: Grain size core
M: Matrix spike sample or core
P: PCB core
X: X-Ray core

[3] Same as Paradox

Table 3-93
Data Dictionary for Table SEDDESC in *PHASE2\HRCORES* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
TAMS ID	tams_id	A13	Sample identifier
TAMS Type	tams_type	A3	Sample type [2]
Eh	[3]	N	Redox potential in meV
Temperature	temperatux	N	Temperature of redox measurement in EC
Field Comment	field_comx	A50	Comments from field notes
Percent Solids	percent_sx	N	Percent solids by dry weight
Bulk density (g/cc)	bulk_densx	N	Calculated bulk density in g/cc
Part. density (g/cc)	part_densx	N	Calculated particle density in g/cc

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[2] A: Archive core
B: Field blank
D: Duplicate core
G: Grain size core
M: Matrix spike sample or core
P: PCB core
X: X-Ray core

[3] Same as Paradox

Table 3-94
Data Dictionary for Table FLOW93 in *PHASE2\FLOW* Subdirectory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Date	date	D	Measurement data
Fort Edward Meas. Flow	fort_edwar	N	Reported USGS flow at Fort Edward in cfs
Stillwater Calc. Flow	stillwater	N	Calculated flow at Stillwater in cfs [2]
Model-Stillwater	model_stil	A4	Model used to calculate flow at Stillwater [2]
Waterford Calc. Flow	waterfordx	N	Calculated flow at Waterford in cfs [2]
Model-Waterford	model_wate	A4	Model used to calculate flow at Waterford [2]

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[2] These flows were modelled based on the reported flow at Fort Edward and the Champlain Canal staff gauge data contained in *NYSDOT\GAUGES*.
These models will be explained in the Phase2 Data Evaluation and Interpretation Report.

Table 3-95
Tables in NOAA Directory

Table Name	Description
STATIONS	Ecological Survey stations
COORDS	Coordinates for stations
FISH	Sample composition information - fish
PCBFISH	PCB congeners/homologue sum/Aroclor concentrations - fish
PCBFISHD	PCB congeners - fish duplicate pairs/dilution analyses
NONPCBB	Non-PCB data - biota
SPECIES	Key to species codes

Table 3-96
Data Dictionary for Table STATIONS in NOAA Directory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Station	[2]	A8	Station number
TAMS ID	tams_id	A11	Sample identifier
TAMS Type	tams_type	A4	Sample type [3]
Species	[2]	A4	Species code
Date Sampled	date_sampl	D	Sample date
Est Easting	est_eastin	N	Estimated NY State Plane easting (ft)
Est Northing	est_northi	N	Estimated NY State Plane northing 9ft)
River Mile	river_mile	N	Mile measured from the Battery
Description	descriptio	A26	Station description
Program	[2]	A4	Program abbreviation (EC) [4]
SAS No.	sas_nox	A8	Sample identifier for laboratory program
Comment.	comment	A120	Sample comment

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[2] Same as Paradox

[3] B: Field blank
D: Duplicate sample
N: NOAA sample

[4] EC: Ecological survey

Table 3-97
Data Dictionary for Table COORDS in NOAA Directory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Station	[2]	A16	Station name
Est Easting	est_eastin	N	Estimated NY state plane easting (ft)
Est Northing	est_northi	N	Estimated NY state plane northing (ft)
Sample Type	sample_typ	A23	Type of sample taken
Fish Type	fish_typ	A18	Type of fish taken

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] Same as Paradox

Table 3-98
Data Dictionary for Table FISH in NOAA Directory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
TAMS ID	tams_id	A11	Sample identifier
TAMS Type	tams_type	A3	Sample type [2]
Species	[3]	A8	Species code
SAS No.	sas_nox	A8	Laboratory identifier
Noincomp	[3]	A3	Number of fish in composite
Length	[3]	N	Length in centimeters
Weight	[3]	N	Weight in grams
Sex	[3]	A1	Sex

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[2] B: Field blank
D: Duplicate sample
N: NOAA sample

[3] Same as Paradox

Table 3-99
Data Dictionary for Table PCBFISH in NOAA Directory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
TAMS ID	tams_id	A11	Sample identifier
TAMS Type	tams_type	A3	Sample type [2]
Species	[3]	A4	Species code
Split	[3]	A10	Field denoting if record represents a composite of duplicate analyses (Avg-FD - average of field duplicates)
Matrix	[3]	A8	Sample matrix (SED, BIOTA)
Parameter	[3]	A28	Parameter name
Units	[3]	A10	Units of result
Value1	[3]	N	Numerical result with non-detected values set to sample quantitation limit [4]
Value2	[3]	N	Numerical result with non-detected values set to 0 of 1/2 quantitation limit
Qualifier	[3]	A6	Data qualifier
QA Comment	qa_comment	A10	Quality Assurance comment code see PHASE2\QUALIFY
Validated?	validated	A4	Field denoting if results have been validated (Yes/No)

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[2] B: Field blank
D: Duplicate sample

[3] Same as Paradox

[4] Homologue sums and Total PCBs values represent sums of detected values only.

Table 3-100
Data Dictionary for Table PCBFISHD in NOAA Directory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
TAMS ID	tams_id	A11	Sample identifier
TAMS Type	tams_type	A4	Sample type [2]
Matrix	[3]	A8	Sample matrix (BIOTA)
Parameter	[3]	A28	Parameter name
Units	[3]	A10	Units of result
Species	[3]	A4	Species code; see SPECIES table for definition of codes
Value	[3]	N	Numerical result with non-detected values set to sample quantitation limit
Qualifier	[3]	A6	Data qualifier
QA Comment	qa_comment	A10	Quality Assurance comment code see PHASE2\QUALIFY

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[2] B: Field blank
D: Duplicate sample
N: NOAA sample

[3] Same as Paradox

Table 3-101
Data Dictionary for Tables NONPCBB in NOAA Directory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
TAMS ID	tams_id	A11	Sample identifier
TAMS Type	tams_type	A3	Sample type [2]
Species	[3]	A4	Species code
SAS No.	sas_nox	A8	Sample identifier for laboratory program
Split	[3]	A10	Field denoting if record represents a composite of duplicate analyses (Avg-FD - average of field duplicates)
Laboratory	[3]	A10	Name of laboratory performing analysis
SDG No.	sdg_nox	A12	Sample delivery group (for data validation)
Parameter	[3]	A30	Parameter name
Units	[3]	A4	Units of result
Value	[3]	N	Numerical result with non-detected values set to sample detection limit
Qualifier	[3]	A4	Data qualifier
Validated	[3]	A4	Field denoting if results have been validated (Yes/No)

[1] A: character field with number denoting size of field
 D: date field
 N: number field
 M: memo field

[2] B: Field blank
 D: Duplicate sample
 N: NOAA sample

[3] Same as Paradox

Table 3-102
Data Dictionary for Table SPECIES in NOAA Directory

Field Name Paradox	Field Name FoxPro	Field Type [1]	Description
Species	[2]	A8	Species code
Definition	[2]	A20	Definition of species code

[1] A: character field with number denoting size of field
D: date field
N: number field
M: memo field

[2] Same as Paradox

PCBS Table

TAMS ID	TAMS Type	Split	Matrix	Parameter	Units	Value 1	Value 2	Qualifier	QA Comment	Validated
HR-001-00002	P		SED	BZ#8	µg/Kg DW	9.25	9.25	J	GP	Yes
HR-001-00002	P		SED	BZ#22	µg/Kg DW	8.09	8.09	J	G	Yes
HR-001-00002	P		SED	BZ#87	µg/Kg DW	6.64	6.64	J	QHS	Yes
HR-001-00002	P		SED	BZ#180	µg/Kg DW	6.51	6.51	JN	GST	Yes

STATIONS Table

Station	TAMS ID	TAMS Type	Date Sampled	Lower Depth (cm)	Upper Depth (cm)	Est. Easting (ft)	Est. Northing (ft)	River Mile	Location	Program	SAS No.	Comments
HR-001	HR-001-00002	P	8-23-92	0	2	618700	375750	25	Piermont Marsh 12	HR	SB0618	
HR-011	HR-011-0608	P	9-30-92	8	6	654600	952700	143.5	Albany Turning Basin	HR	SB2143	
HR-027	HR-027-1216	P	9-30-92	16	12	676700	1200550	202.9	Background - Bishop's Dock	HR	SB1206	

NONPCBS Table

TAMS ID	TAMS Type	SAS No.	Split	Laboratory	SDC No.	Parameter	Units	Value	Qualifier	Validated
HR-001-00002	P	SB0618		LDEO	19	TC	%	2.34		Yes
HR-001-00002	P	SB0618		LDEO	19	TN	%	0.2	J	Yes
HR-001-00002	P	SB0618		LDEO	19	C/N	molar	13.6		Yes

Figure 3-1
Examples of One-To Many Relationships from
PHASE2 \HRCORES Database Tables




Figure 3-2
Database Tables in *HISTORIC \SED* Subdirectory




Figure 3-3
Database Tables in *HISTORIC\FISH* Subdirectory

* In *HISTORIC* directory - contains information on all files in this directory




Figure 3-4
Database Tables in *HISTORIC\MACROINV* Subdirectory

* In HISTORIC directory - contains information on all files in this directory




Figure 3-5
Database Tables in *GE* Directory




Figure 3-6
Database Tables in *PHASE2\WATER* Subdirectory

* In PHASE2 directory - reference for information on all files in this directory

** Files located in PHASE2\WATER\QA_QC subdirectory

*** Files located in PHASE2\WATER\EQUILIB subdirectory

TAMS/Gradient




Figure 3-7
Database Tables in *PHASE2\SEDIMENT* Subdirectory

* In PHASE2 directory - reference for information on all files in this directory

** Files located in PHASE2\SEDIMENT\QA_QC subdirectory

TAMS/Gradient




Figure 3-8
Database Tables in *PHASE2\ECO* Subdirectory




Figure 3-9
Database Tables in *PHASE2\HRCORES* Subdirectory

* In PHASE2 directory - reference for information on all files in this directory

** Files located in PHASE2\HRCORES\QA_QC subdirectory

TAMS/Gradient




Figure 3-10
Database Tables in NOAA Directory

* In PHASE2 directory - reference for information on all files in this directory

** Files located in NOAA\QA_QC subdirectory

*** Files located in PHASE2\ECO subdirectory

TAMS/Gradient

HRCORES\NONPCBS (Partial Listing)

	TAMS ID	TAMS Type	Parameter	Value
	√	√		√
Criteria			"C/N"	> 0



PCBS (Partial Listing)

	TAMS ID	TAMS Type	Parameter	Value2
				√
Criteria			Total PCBs	

√ Include field in answer

↓ Link tables

TAMS/ Gradient

Figure 3-11
Table Links for Example Database Query 1

Criteria	HRCORES/STATIONS (Partial Listing)				
	Station	TAMS ID	TAMS Type	Lower Depth (cm)	Upper Depth (cm)
				√	√
	HR-019				



Criteria	PCBS (Partial Listing)			
	TAMS ID	TAMS Type	Parameter	Value2
				√
			Not Like BZ	

√ Include field in answer

↓ Link tables

TAMS/ Gradient

Figure 3-12
Table Links for Example Database Query 2